

Sewing Pattern — Dress 4193

Recommendations on fabric: fabric suitable for dresses. Chiffon for decoration.

You will also need: blind zipper; bias tape (approx. length is mentioned on patterns); small button.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: on hem of the dress and along slit of central part of back part – 2.0 cm; along the lower edge of sleeve, on edge of back part, neckline inset and yokes of back part, yokes of front part, inset of front part – 0 cm. Other seam allowances – 1 cm .

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.

CUTTING:

Main fabric:

1. Central back part - 2 details
2. Side back part - 2 details
3. Back yoke - 2 details
4. Front part yoke - 2 details
5. Side front part - 2 details
6. Central front part – 1 detail
7. Front part inset — 2 details
8. Sleeve - 2 details

Chiffon:

1. Back part inset - 1 detail
2. Lower sleeve part – 2 details



INSTRUCTIONS:

1. Make a slit on back part inset according to markers, pipe it with bias tape, stitch lower corner.
2. Serge middle edges of central back part. Sew middle edge of central back part exactly from marked line of inset connecting line up to marker slit. Press apart the seam, pressing sides of slit. Put the stitch along the slit 0.1 cm off the edge. Stitch inset of back part to central part, press seam allowances downwards and serge.
3. Sew relieve seams on back part. Press seam allowances to side edge and serge. Stitch yoke to back part, press seam allowances upwards and serge.
4. Serge middle edge of front part inset. Sew middle edge of front part inset from top edge up to marker and from marker up to lower edge. Press apart the seam, pressing a slit. Make and fasten counter plaits on top edge according to markers.
5. Stitch inset of front part to central part, press seam allowances upwards and serge. Sew relieve edges of front part. Press seam allowances to side edge and serge. Stitch yoke to front part, press seam allowances upwards and serge.
6. Sew shoulder seams, press seam onto back part and serge. Overstitch the neckline with bias tape. Make a small loop buttonhole from chiffon, sew it to right side of the back part slit. Sew a button on left side slit of the slit.
7. Sew right side edge, press seam onto back part and serge. Serge left side edge separately and sew, leaving the section between notches unsewn. Press seam apart, pressing slit for zipper. Sew in zipper.
8. Sew sleeve with lower part, press seam allowances upwards and serge. Make and fasten plaits according to markers, depths are directed downwards. Overstitch lower edge of sleeve with bias tape. Sew, press and serge edge of sleeve. Sew sleeve into armhole, leveling notches. Press seam allowances towards side of the armhole and serge.
9. Serge seam allowance of the dress hem, press onto wrong side and undersew with invisible stitches.

TECHNICAL DRAWING:

