

Sewing Pattern — Jumper 7010

Recommended fabric: cotton.

You will also need: 10 cm of fusible interfacing of 90 cm wide; 2 buttons of 12 mm in diameter; 8 decorative snaps of 12 mm in diameter; sew-on applique

If the pattern has a double line around it, the seam allowances are included.

Seam allowance: 1 cm on all seams, 3 cm on pant leg hem.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Main fabric:

1. Front - cut 2
2. Back - cut 2
3. Snap placket - cut 2
4. Facing of upper back- cut 2
5. Strap - cut 2
6. Facing of upper front - cut 1 on fold

Apply interfacing to half of the width of the strap

INSTRUCTIONS:

1. Apply interfacing to half of the width of the strap.
2. Sew front center seam, serge and press seam toward right. Sew center back seam, serge a press seam toward left.
3. Sew appliqué on front.
4. Sew side seams, serge and press seam toward back.
5. Cut one end of the strap in corner shape.
6. Fold strap in half lengthwise, right sides together, sew one long and one short side, turn right side out, press and sew along edges with decorative stitch or topstitch at 5 mm.

7. Pin straps, to right side of back according to marks. Sew center back seam. Serge and press seam toward left.
8. Sew sides seams of facings, press seam open. Serge lower edge of facing.
9. Pin facing on main garment, right sides together, and stitch along armholes and upper edge, catching the straps; understitch and turn onto wrong side of garment, press and sew decorative stitch or topstitch at 5 mm along the edge.
10. Serge bottom edge of pant leg. Press onto wrong side and sew decorative stitch or topstitch.
11. Fold one snap placket in half lengthwise, right sides together, sew short edges, turn out and press.
12. Press under open edges of the placket, insert the back leg edge between them and sew on the edge.
13. Fold second snap placket detail in half lengthwise, right sides together, sew short edges, turn out and press.
14. Pin open edge of placket, onto front leg edge from the right side, sew, press placket onto wrong side of the garment, turn under seam allowance and sew a decorative stitch or topstitch on edge.
15. Sew decorative stitch or topstitch along the edge of legs at 5 mm.
16. Set decorative snaps on plackets, according to marks.
17. Make buttonholes on front according to marks; sew buttons on straps.
18. Make tucks on front sides according to marks and set decorative snaps.

TECHNICAL DRAWING:

