

Sewing Pattern — Dress 4055

Recommendations on fabric: thick fabric suitable for dresses, decorating fabric.

You will also need: lining; fusing; blind zipper; 2 buttons of 1 cm diameter; 5 buttons of 2 cm diameter.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams -1 cm; on hem – 3 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric:

1. Upper back part - 2 details
2. Central lower back part – 2 details
3. Side lower back part – 2 details
4. Central upper front part – 1 detail
5. Side upper front part – 2 details
6. Central lower front part – 1 detail
7. Side lower front part – 2 details
8. Left facing of back part - 2 details
9. Right facing of back part - 2 details
10. Strap - 2 details

Decorating fabric:

1. Back part inset - 2 details
2. Front part inset - 1 detail

Lining:

1. Upper back part lining - 2 details
2. Central upper front part – 1 detail
3. Side upper front part – 2 details

Fusing:

1. Back neckline facing - 2 details

INSTRUCTIONS:

1. Apply fusing to back part neckline facing.
2. Sew relieve edges on details of lower back part, press seam allowances to middle edge and serge. Stitch back part inset to lower part, press seam allowances upwards and serge. Stitch upper back part to inset, press seam allowances downwards and serge.
3. Sew middle edge of back part, press seam allowances and serge. Press left part of back part on middle line, making a plait.
4. Sew relieve edges on details of lower and of upper front part, press seam allowances towards center of front part and serge. Stitch inset of front part to lower part, press seam allowances upwards and serge. Stitch upper front part to inset, press seam allowances downwards and serge.
5. Sew right side edge, press seam onto back part and serge. Serge edges of left side seam. Sew left side edge from zipper marker downwards, press seam allowances apart. Sew in zipper.
6. Fold strap in half lengthwise right sides together and overstitch longer edge. Turn onto right side and press.
7. Sew middle edge of back part on lining details, relieve edges of front part and right side edge. Press seam allowances and serge. Serge lower and left side edges.
8. Fold lining with garment right sides together and overstitch neckline and armholes edge of front part, upper edge of back part, inserting lower side of strap. Slash seam allowances on rounded parts, turn lining onto wrong side. Topstitch lower edge of lining into connecting seam of upper back and front parts.
9. Fold back part neckline facings wrong sides together and overstitch neckline edge and middle edge exactly up to marked line of lower edge. Slash seam allowances, turn the facing onto right side, press. Press lower edges of outer and inner facings onto wrong side on 1 cm.
10. Fold outer facing with front part on shoulder edge, wrap with inner facing and sew. Turn the facing onto right side, straighten, coincide lower folds, insert top part straps between them and sew.
11. Press seam allowance of hem of the dress onto wrong side on 1 cm, then again on 2 cm and topstitch.
12. Serge buttonholes on neckline facing as marked, sew buttons according to buttonholes. Sew buttons on back part.

TECHNICAL DRAWING: