

## Sewing Pattern — Dress 4037

Recommendations on fabric: natural or mixed fabric suitable for dresses

You will also need: fusing; lining; 7 buttons

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams - 1 cm; hem of the garment - 2 cm; lower edge of sleeve – 1.2 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING:**

#### Main fabric:

1. Central upper back part – 2 details
2. Side upper back part – 2 details
3. Back part inset – 1 detail
4. Central lower back part – 2 details
5. Side lower back part – 2 details
6. Side lower front part – 2 details
7. Central lower front part – 2 details
8. Front part inset – 2 details
9. Side upper front part – 2 details
10. Central upper front part – 2 details
11. Stand-up part of collar – 2 details
12. Buttonstand – 2 details
13. Sleeve – 2 details
14. Belt – 1 detail

#### Lining:

1. Back part inset – 1 detail
2. Front part inset – 2 details

Fusing: buttonstand, stand-up part of collar, back part inset, front part inset

### **INSTRUCTIONS:**

1. Apply fusing to buttonstand, stand-up part of collar, back part inset, front part inset.
2. Sew center edges of upper and lower parts of the back, press seam onto left side and serge. Put double decorative stitch at 0.1 and 0.7 cm off the connecting seams. Sew princess edges of upper and lower parts of the front / the back. Press seam allowances towards center and serge. Put double decorative stitch at 0.1 and 0.7 cm off the connecting seams.
3. Sew side seams of upper parts of the back / the front, press seam onto back part and serge. Sew side seams of lower parts of the back / the front, press seam onto back part and serge.
4. Sew side seams of insets, press seam allowances apart. Serge belt slits on the inset according to markers. Sew side seams of back part / front part insets which are from lining. Press seam allowances apart. Serge lower edge.
5. Fold inset of main fabric and of lining along top edge right sides together, insert upper part of the dress between them and sew. Fold insets downwards. Stitch lower part of the dress to the inset of main fabric. Press seam allowances onto inset. Topstitch lower serged edge of inset lining into connecting seam of main fabric inset to lower part of the dress. Put double decorative stitch at 0.1 and 0.7 cm off the inset connecting seams.
6. Sew shoulder seams. Press seam allowances towards back part and serge.
7. Sew short sides of outer stand-up part of collar into the neckline. Slash seam allowance in corner. Sew stand-up part of collar into the neckline of back part / front part, press seam onto stand-up part of collar. Stitch inner stand-up part of collar to buttonstands, press seam allowances apart. Serge outer edge of buttonstand and inner stand-up part of collar, turn inside onto wrong side and topstitch. Put buttonstand with stand-up part of collar onto right side of front part right side downwards and overstitch along buttonstand line and along top edge of the stand-up collar. Slash seam allowances on rounded parts, slash away in corners.
8. Stitch lower edges of buttonstands to front part exactly on marked hem line. Cut seams of lower corners of buttonstand. Turn front bands right side out, straighten and press the seams. Topstitch inner stand-up part of collar into connecting seam of outer stand-up part of collar. Put decorative stitch along front band and along edge of the stand-up collar.
9. Serge lower edge of sleeve. Press hem onto wrong side and put double decorative stitch at 0.3 and 1.0 cm off the edge. Slash seam allowances of armholes near notches, sew sleeves into armholes, serge. Serge seam allowances of lower part of the armhole, turn inside and topstitch.
10. Serge hem of garment. Press hem onto wrong side and put double decorative stitch at 1.0 and 1.7 cm off the hem.
11. Serge buttonholes on right front part. According to them sew buttons on left front part.
12. Fold detail of the belt in half lengthwise right sides together and overstitch on long and one short sides. Turn belt right side out, turn inside seam allowances of unsewn section and put double decorative stitch at 0.1 and 0.7 cm along the perimeter of the belt.

**TECHNICAL DRAWING:**

