

Sewing Pattern — Dress 4278

Recommendations on fabric: fabric suitable for dresses;
contrast fabric for decoration

You will also need: blind zipper, fusing

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams 1 cm; hem of the dress –
1.5 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Upper back part - 2 details
2. Lower back part - 1 folded detail
3. Upper front part - 1 detail
4. Lower front part - 1 folded detail
5. Back neckline facing – 1 detail
6. Front neckline facing – 1 detail

Fabric for decoration:

1. Back part inset - 1 detail
2. Back part decoration - 1 folded detail
3. Front part inset - 1 detail
4. Front part decoration - 1 folded detail

Fusing:

1. Back neckline facing – 1 detail
2. Front neckline facing – 1 detail

INSTRUCTIONS:

1. Apply fusing to details of neckline facings.
2. Sew darts on upper parts of the back, press depths to center edge. Sew center edge of upper back part, press seam onto left side and serge. Stitch back part inset to upper back part, press seam onto inset and serge.
3. Stitch decoration of back part to lower back part, press seam onto decoration and serge. Make and fasten according to markers counter plaits. Stitch lower back part to upper part, press seam allowances upwards and serge.
4. Sew darts on of upper front part, press depths of waist darts towards center, bust darts - upwards. Stitch front part inset to upper front part, press seam onto inset and serge.
5. Stitch decoration of front part to lower front part, press seam onto decoration and serge. Make and fasten according to markers counter plaits. Stitch lower front part to upper part, press seam allowances upwards and serge.
6. Serge separately left side edges, sew them from the notch downwards, press seam allowances apart. Sew in the zipper. Sew right side edge, press seam onto back part and serge. Sew shoulder seams, press seam allowances onto back part.
7. Sew shoulder and right side edges of the facings. Press apart seam allowances. Serge left side and outer edges of the facing. Fold dress with facing right sides touching and overstretch the neckline. Slash seam allowances on rounded parts, turn the facing out, straighten and press. Overstretch armhole in two steps: first back part, then front part. Slash seam allowances on rounded parts, turn out, press. Fix the facing to the garment along right side and center seam allowances. Fasten the facing to zipper tape.
8. Serge lower edge of the dress, press onto wrong side and topstitch.

TECHNICAL DRAWING:

