

## Sewing Pattern — One-piecer 4021

Recommendations on fabric: jeans fabric with elastane

You will also need: zipper of 8 cm long, 8 buttons, cotton lining or pocket bags, 2 clasps of 4 cm wide.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams - 1 cm, on top edge of back pocket — 3.5 cm, on hem – 4 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING:**

#### Fabric:

1. Back half — 2 details
2. Back side part - 2 details
3. Bag middle part - 2 details
4. Front right part - 1 detail
5. Front left part - 1 detail
6. Front side part - 2 details
7. Left front half - 1 detail
8. Right front half - 1 detail
9. Side-body - 2 details
10. Button catch - 1 detail
11. Back pocket - 2 details
12. Top edge acing – 1 detail
13. Left buttonstand– 1 detail
14. Right buttonstand– 1 detail
15. Big strap - 4 details
16. Small strap — 2 details
17. Fly piece — 1 detail

#### Lining:

1. Pocket bag — 2 details

Attention: Along some seams put double stitch at 0.1 and 0.7 cm off the seam. Interfacing is not used for this one-piecer.

## **INSTRUCTIONS:**

1. Serge upper edge of back pocket. Press top seam allowance of pocket onto wrong side. Put double stitch on pocket marking. Mark pocket location on back half. Topstitch pocket with double stitch.
2. Sew back side and back middle part. Serge seam, press towards center of back part and put double stitch. Stitch back half to back side and middle parts. Serge seam, press upwards and put double stitch. Sew back middle edge. Serge seam, press onto left side and put double stitch.
3. Serge round edge of side-body. Put side-body with its wrong side onto right side of pocket bag and topstitch according to markers. Fold pocket bag with front half right sides together and overstretch pocket opening. Slash seam on rounded parts, turn details out, press and put double stitch along pocket opening. Fold pocket bag in half. Sew and serge lower edge of pocket bag. Fasten together front part and pocket along side and top edge.
4. Serge outer edge of fly piece. Stitch fly piece to right front half. Sew middle edge of front halves, starting the stitch near fly piece connecting edge. Trim seam, serge and press onto right half. Press fly piece onto wrong side. Align zipper with middle edge of left half and stitch. Fold button catch in half lengthwise right sides together and sew short lower edge. Turn button catch out, press and sew longitudinal edge. Serge longitudinal edge of button catch. Stitch button catch to zipper connecting seam to left half. Stitch loose tape of zipper to fly piece on right half. Put decorative stitch on marked line on right half of pants at 0.1 and 0.7 cm. Staystitch on closure end from right side of pants, fastening together fly piece and button catch.
5. Sew front middle and side parts. Serge seam, press towards front center and put double stitch. Serge outer edge of buttonstands, press them inside at 1 cm and topstitch. Fold buttonstands with corresponding details right sides together and stitch. Start the stitch exactly from front half connecting line and end, leaving 5 cm to top corner. Unfold details, lay out in one layer, pressing seam allowances towards buttonstand. Stitch front half to middle and side parts, without catching buttonstand. Serge seam and press it upwards. Turn buttonstands onto wrong side and turn under lower edge, rounding seam allowance. Put double stitch along seam, catching lower edge of buttonstand.
6. Sew side seams. Press seam allowances onto back part, serge.
7. Sew leg edge. Serge seam and press it towards back part.
8. Serge lower edge of top edge facing, press inside at 1 cm and topstitch. Turn top part of buttonstands onto wrong side, level to edges of front part, put upper edge facing on top and overstretch middle edge, corners and upper edge of one-piecer. Slash details in corners and trim, turn out and press. Put decorative stitch along front and top edge of the garment at 0.2 cm. Fasten lower edge of facing with 2-3 tucks to buttonstands and to side seams.
9. Press hem seam allowance onto wrong side first at 1 cm, then at 3 cm and topstitch.
10. Fold small strap in half right sides together and overstretch, leaving a slit open at 5 cm off the fold. Slash seam allowances in corners, turn details out, press and stitch at 0.2 cm off the edge, stitching the slit closed. Run upper end of strap through the clasp and topstitch.
11. Fold details of big strap pairwise and overstretch separately right and left details. Start and end the seam exactly near marked line of center edge connection. Trim details in corners, turn out and press. Sew middle edge of inner straps. Press seam apart. On outer side of straps insert middle edge of left strap into right one, turn under open edge of right strap and topstitch at 0.1 cm off the fold. Put decorative stitch along contour of straps at 0.2 cm off the edge.
12. Make buttonholes on one-piecer and on straps according to markers. Sew buttons on one-piecer along buttonstand and near top edge.

**TECHNICAL DRAWING:**

