

## Sewing Pattern — Dress 4191

Recommendations on fabric: dress fabrics with elastane of natural or mixed fibers.

You will also need: elastic lace 10 cm wide; decorative piping (approximate length is shown on upper front part pattern); bias tape.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: on hem - 2 cm; on hem of sleeve - 0 cm; other seams - 1 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING:**

Fabric:

1. Front part 1 – 1 detail
2. Front part 2 – 1 detail
3. Front part 3 – 1 detail
4. Front part 4 – 1 detail
5. Front part 5 – 1 detail
6. Lower front part – 1 detail
7. Back part – 2 details

Lace:

1. Sleeve – 2 details

### **INSTRUCTIONS:**

1. Sew darts on back part. Press depths to the center. Sew and serge middle edge of back part. Press allowance to the left side. (If fabric is not stretchy enough, sew a zipper into middle seam of back part).
2. Sew a dart on front part2. Press the depth upwards.

3. Cut lace according marking on front part. Fix lace to front part details along open edges.
4. Sew and serge relieve edges of front part, starting from lower part, inserting decorative piping between details. Press seams upwards and serge.
5. Sew right shoulder edge. Serge allowance and press it to the back part.
6. Cut a bias tape of neckline length. Fold bias tape in half lengthwise right side out and press. Fold bias tape with neckline from right side and overstretch, turn bias tape to the wrong side, slash seams and topstitch onto main detail along fold line. Press the seam. Sew left shoulder edge. Serge allowance and press it to the back part.
7. Sew sleeves in armholes. Serge allowances. Sew round lower part of armhole with bias tape. Sew and serge side edges.
8. Serge hem of the garment, turn it inwards and undersew with blind stitches.

**TECHNICAL DRAWING:**

