

Sewing Pattern — Skirt 5152

Recommendations on fabric: well-forming material for skirts / fabric of 150 cm width

You will also need: fusing; 1 zipper of 20 cm length, 2 zippers of 90 cm length.

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Back panel - 2 details
2. Front panels - 2 details
3. Front panel facing - 1 folded detail
4. Back panel facing - 2 details
5. Gusset - 2 details
6. Pocket - 1 detail
7. Flap - 2 details

Fusing: facings, upper details of flaps.

INSTRUCTIONS:

1. Strengthen the facings and upper details of flaps with fusing (press thermal interfacing on the left side with hot iron).
2. Sew darts into back panel, press towards center.
3. Sew back center seam below zipper mark, press allowance apart. Tack zipper under split edges, sew it from the right side.
4. Sew front center seam, press allowance apart.

5. Press pocket allowance into wrong side and sew it on the front right panel according to marking. Work sides and lower edge of the flap, tuck and press it. Sew the flap on front right panel above the pocket. Press downwards and topstitch on 0.7 cm distance from edge.
6. Sew side seams from the zipper mark down to slit marks.
7. Sew side seams of facings.
8. Work waistline with facings. Press allowance on facing and topstitch, tuck and tack the open edge of facing. Fold facing ends under and sew to zipper bands.
9. Tack zippers under side split edges so that they open upwards and topstitch along the edge.
10. Fold gusset hem allowances under and topstitch. Put chocks on zippers bands and side seam allowances right sides to left and topstitch closely to zipper teeth.
11. Turn over hem allowance along hemline, press and sew by hand.

TECHNICAL DRAWING:

