

Sewing Pattern — Dress 5129

Recommendations on fabric: batiste with crepe effect of 150 cm width

You will also need: 1 zipper of 60 cm length

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams, 2 cm on center fronts and hem.

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches. They must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Fabric:

1. Front left– cut 1
2. Cross-over front right (flying part on pattern) – cut 1
3. Back – cut 2
4. Armhole bias – cut 2
5. Tie – cut 2

INSTRUCTIONS:

1. Sew darts. Press bust darts downward, and waist darts toward center.
2. Serge center back edges separately. Sew center back seam from zipper mark down to hem.

3. Serge and press the allowance of the front right side diagonal edge onto wrong side, then topstitch.
4. Sew left shoulder seam, serge and press toward back.
5. Serge front and back neckline edge, press onto wrong side, and topstitch.
6. Press center back seam apart, including opening for zipper. Sew in zipper.
7. Place flying front over front right side, matching front middle lines and front neckline edge with flying front marks. Sew right armhole edges and right side edges to diagonal part.
8. Sew right shoulder seam, leaving neckline edge extended. Serge and press seam forward.
9. Fold each strip of bias tape for the armhole along the center and press. Sew raw edges of bias tape to right side of armhole edge. Trim seam, turn the bias tape onto wrong side, and topstitch along the folded edge from the right side of the garment.
10. Fold ties in half, right sides together. Sew ties 1 cm from fold. Trim seam and turn right side out. Sew one end of the tie to left side edge of front, between crosswise marks.
11. Sew side seams. Serge and press seam toward back. Tack seam allowance under armhole with a few stitches.
12. Serge lower edge of garment, turn onto wrong side, and topstitch or sew with invisible stitches, if desired.
13. Serge the diagonal edge of flying front, then turn seam allowance onto wrong side. Serge front edge, then press onto wrong side. Topstitch the flying front diagonal edge and front edge at 0.1 cm.
14. Sew the second tie under the corner of flying front, between crosswise marks.

TECHNICAL DRAWING:

