

Sewing Pattern — Trousers 5127

Recommendations on fabric: natural or mixed, suit fabric of 150 cm width

You will also need: 1 zipper of 22 cm length.

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

- 1. Middle front part 2 pieces
- 2. Side front part 2 pieces
- 3. Back part 2 pieces
- 4. Back facing 1 piece
- 5. Front facing 2 pieces
- 6. Button catch 1 piece

Fusing: facing details.

INSTRUCTIONS:

- 1. Apply the fusing to wrong side of facings.
- 2. Sew darts. Press dart depths towards the center
- 3. Sew front relieves to notch mark. Press allowances apart.
- 4. Sew side seams. Sew leg inside seams. Press allowances apart. With one stitch, sew front and



back middle seams, leaving closure slit unsewn. Press allowances apart from the top to place where roundings begin.

5. ZIPPER: Press one-piece facing for zipper into wrong side. Stitch the zipper under the closure allowance edge (left side) along the edge. Stitch zipper free braid to right side, to one-piece facing.

Fold the button catcher along the center, overstitch it along upper and lower short ends. Topstitch the zipper closure one-piece facing on the button catch on the left part of the trousers. Stitch along the skit right edge, catching the facing.

- 6. TROUSERS UPPER PART: sew facings along side edges. Topstitch fading on the upper edges of parts, right sides together. Cut the allowances to 0.5 cm width, place them under facings, them stitch along the edge. Turn facing into wrong side, then press the upper edge. Turn the facing from inside, then sew on the zipper braid. Additionally: sew facings lower edges to seam allowances and darts depths.
- 7. HEMS: turn hem allowances into wrong side, then sew.

TECHNICAL DRAWING:

