

Sewing Pattern — Blouse 5105

Recommendations on fabric: knitted fabric of 140 cm width.

You will also need: fusing.

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Front part - 1 folded detail
2. Back part - 2 details
3. Sleeve - 2 details
4. Neckline facing - 2 folded details

Fusing: neckline facing.

INSTRUCTIONS:

1. Apply fusing to outer detail of the knitted panel. (Adhesive pads are pressed on wrong side of the detail with a very hot iron).
2. Sew middle seam of back part and side seams. Press seam allowances apart.
3. Sew sleeve seams. Press seam allowances on sleeve hem onto wrong side and topstitch by 2 cm with double needle.
4. Sew sleeves in open armholes. Press seam allowances in top parts of armhole seams onto front and back parts.
5. Fold outer and inner details of neckline facing in half right side together, pin and sew back middle edges. Press seam allowances apart. Fold both panel details right sides together and pin neckline edges. Sew. Cut seam allowances close to the stitch, slash on roundings and on front part center line. Turn the panel out. Serge the edge and press, tack open edges. To protect front part corner from sluffing, press a small pad cloth on front part wrong side over marked line of panel connection seam. Pin panel in the neckline from front part center line up to middle seam of back part, coinciding marked lines of panel connection seam with cross

- marks. Outer detail of the panel lies on right side of the garment. Sew panel in, fasten the seam at the beginning and at the end. Slash seam allowance of front part on front part center line to last stitch. Pin and sew second half of front part in the neckline from front part center line up to middle seam of back part. Fasten at the beginning and at the end. Serge allowances of panel connection seam and press onto front part, back part and sleeve.
6. Press seam allowance on hem of the blouse onto wrong side and topstitch by 2 cm with double needle.

TECHNICAL DRAWING:

