

Sewing Pattern — Blouse 5095

Recommendations on fabric: light-weight, well-draping blouse fabric (crepe)

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowance: 1 cm

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Main fabric:

1. Front - cut 1 on fold
2. Back - cut 1 on fold
3. Sleeve - cut 2
4. Bias tape for neckline casing - cut 1 on fold
5. Tie for neckline- cut 4
6. Sleeve ruffle *pattern name: “sleeve facing” - cut 2
7. Front slit facing - cut 1

INSTRUCTIONS:

1. Serge edges of slit facing. Pin slit facing to front, right sides together, along line for slit, and sew on three sides very close to the line. Snip facing and front between stitches. Turn the facing onto wrong side, press slit edges. Topstitch close to edges.

2. Sew side seams. Serge and press toward back. Sew sleeve seams. Serge and press.
3. Sew ruffle together along short side. Serge seam allowance. Serge lower edge of sleeve ruffle. Turn under and topstitch. Slightly gather the top edge of ruffle. Adjust the gathers to fit lower edge of sleeve. Sew ruffle to lower edge of sleeve. Serge seam allowance.
4. Sew sleeves into open armholes. Serge allowances of sleeve connecting seam together and press onto the sleeve in lower part of the armhole.
5. Serge neckline edge and press seam allowance onto wrong side, and topstitch.
6. On neckline casing, press long edges and short edges of seam allowances onto wrong side. Pin the casing to wrong side of the blouse according to markers, aligning ends of the casing with front slit edges. Topstitch along both sides the casing according to markers.
7. Sew the tie pieces together, fold in half and sew lengthwise at 0.5 cm from fold. Turn right side out. Run it through the neckline casing. Knot ends.
8. Serge lower edge of blouse, turn under, and topstitch at 1.5 cm.

TECHNICAL DRAWING:

