

Sewing Pattern — Blouse 5094

Recommended fabric: viscose, light-weight blouse fabric

You will also need: fusible interfacing; 6 buttons.

If the pattern has a double line around it, the seam allowances are included.

Seam allowance: all seams 1 cm, hem 2 cm.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.



CUTTING:

(The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.)

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Main fabric:

1. Back - cut 1 on fold
2. Front - cut 2
3. Collar -cut 2
4. Collar-stand -cut 2
5. Sleeve - cut 2
6. Cuff - cut 4
7. Front button placket - cut 2

Fusible interfacing: button plackets (use *placket fusing* pattern piece), cuffs, 1 collar and 1 collar-stand

INSTRUCTIONS:

1. Apply fusible interfacing to outer half of button plackets (use placket fusing pattern piece), outside cuffs, outer collar, and outer collar-stand.
2. Sew darts, press bust darts downward and vertical darts toward center. Sew side and shoulder seams. Serge and press seams toward back.
3. Press seam allowance under on side of button placket without interfacing. Pin placket to front, right sides together, and sew. Press seam toward placket. Press along placket center line. Topstitch along front connecting seam, catching lower side of the placket.
4. Serge bottom edge of blouse, turn and topstitch.
5. Sew collar, right sides together, along outer edges. Turn and press. Pin collar-stand, right sides together, inserting the ready collar between upper edges and sew. Turn and press. Sew outer collar-stand into neckline, turn under seam allowance of inner collar-stand and sew to connecting seam. Make a buttonhole on right end of collar-stand.
6. Serge both edges of sleeve separately. Sew sleeve seam to slit marker, press seam allowances apart. Topstitch seam allowance of slit. Make and tack pleats along lower edge of sleeve. Pin cuff, right sides together, and sew outer edges. Trim corners, turn and press. Sew outer cuff to lower edge of sleeve, turn inner cuff seam allowance under, and topstitch into connecting seam.
7. Make a gathering stitch along sleeve cap. Sew sleeve into armhole, matching marks and easing along cap. Serge and press seam allowances.
8. Make 5 buttonholes on right front button placket, make 1 buttonhole on each cuff. sew buttons on left.

TECHNICAL DRAWING:

