

Sewing Pattern — Coat 5085

Recommendations on fabric: crepe of 150 cm width

You will also need: lining of 140 cm width; fusible interfacing;
5 buttons of
30 mm diameter; shoulder pads

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams, 2 cm on sleeves hems

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches. They must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Fabric:

1. Back hem facing – cut 1
2. Front hem facing – cut 1
3. Back – cut 1
4. Back neck facing – cut 1
5. Front – cut 2
6. Front facing bands – cut 2
7. Upper sleeve – cut 2
8. Lower sleeve – cut 2

Lining:

9. Back – cut 2
10. Front – cut 2
11. Upper sleeve – cut 2

12. Lower sleeve –cut 2

Interfacing: apply the interfacing to wrong side of front facing bands, back neck facing, back/front hem facings. Additionally, apply interfacing to back hem allowance.

INSTRUCTIONS:

1. Mark and sew darts, press toward center.
2. Sew shoulder seams, press apart. Sew side seams to slit marks.
3. Sew shoulder seams of front facing bands to back neck facing. Sew side seams of back and front hem facings. Carefully serge or finish inside edge of hem facings. Pin facings to lower edge of coat and sew. Understitch, trim corners, and turn onto wrong side of coat. Slip-stitch in place.
4. Pin front facing bands/neck facing to fronts and neckline; sew, clip into curves, turn right side out and press.
5. Apply the interfacing to wrong side of sleeve hems. Sew elbow seam, and front sleeve seam. Press allowances apart and turn sleeves right side out. Press sleeve hem allowances onto wrong side.
6. Make a gathering stitch along sleeve cap for ease. Pin sleeves to the garment matching marks and adjusting ease and sew. Sew in shoulder pads.
7. On lining, make a free-fit pleat and fix it under neckline and few centimeters above garment hem. Sew darts on lining pieces. Sew lining seams to slit mark. Sew the lining to sleeve hems, front facing band, and outer edge of back neck facing. Serge lower edge of back and front lining, press onto wrong side and topstitch. Turn seam allowance under along slit opening and slip-stitch to hem facings along slits.
8. Make buttonholes on right front, sew buttons on left one.

TECHNICAL DRAWING:

