

## Sewing Pattern — Coat 5074

Recommended fabric: fabric of 150 cm width suitable for coats.

You will also need: fusible interfacing; lining of 140 cm width; 5 buttons of 20 mm diameter; 6 buttons of 15 mm diameter; shoulder pads.

If the pattern has a double line around it, the seam allowances are included.

Seam allowance: 1 cm on all edges. Seam allowance at hem — 1.5 cm.

**Note:** By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

**Attention!** First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must coincide.

### **CUTTING:**

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

### **Main fabric:**

1. Pocket flap – cut 2
2. Center back – cut 2
3. Side back – cut 2
4. Side front – cut 2
5. Back neck facing – cut 1
6. Pocket facing – cut 4
7. Collar – cut 2
8. Center front – cut 2
9. Front facing – cut 2
10. Upper sleeve – cut 2
11. Lower sleeve – cut 2



### Lining:

Cut pieces using main pattern pieces. Cut front-- excluding front facing width. Cut lower sleeves with seam allowance only. Cut back-- excluding the width of back neck facing.

12. Upper pocket sacking – cut 2
13. Lower pocket sacking – cut 2
14. Flap – cut 2

Fusible Interfacing: apply interfacing to wrong side of front facings, back neck facing, inner collar and flaps. Also apply interfacing to back hem allowance.

### **INSTRUCTIONS:**

1. Sew center back seam down to the vent. Press vent one-piece facing (left edge) onto wrong side along fold line, then sew to hem allowance; topstitch left side along seam. At vent's right edge, press one-piece facing onto wrong side, sew to hem allowance. Pin the vent along matching lines.
2. Sew side backs to center back, press seam apart. Sew side fronts to center fronts, press seam apart.
3. Making double welt pockets: sew flap lining and main flap, right sides together along side/lower edges, turn right side out, press, topstitch. Apply a strip of 4 cm wide interfacing to wrong side of front (above pocket marking). Lay two pocket facings on front, right sides together. Pin along pocket entrance marking and stitch (lengthwise edge of facings must line up with middle line of pocket marking). Cut front between stitches, snipping diagonally toward stitch ends. Do not cut through facing! Press facing onto wrong side of garment making a neat frame, then tack (facing folds meet at center of pocket entrance.) Topstitch along joining seams. Turn small triangle at slit ends onto wrong side and stitch strictly to facings between upper stitch ends and lower stitch ends. Sew together on facing side seam. Insert flap between welts on front side, line flap edge up with inner top welt seam and sew to the seam allowance. Sew lower pocket sacking on wrong side to lower facing, adjust upper pocket sacking length and sew to top facing. Sew sides of pocket sacking. On front, stitch along sides of welt to finish sewing together the sacking. There are several ways to sew this style pocket. Here is a great video tutorial for making an easy [double welt pocket with a flap](#).
4. Sew shoulder/side seams. Press seams apart.
5. Sew inner collar to neckline. Sew shoulder seams of back neck facing and front facings. Sew outer collar to neckline facing, clip into curves and press seam apart.
6. Pin outer collar with front facings, to the garment, right sides together, and sew. Understitch where possible, turn right side out and press. Sew outer collar's edge on neckline. On right side: turn collar right side out, tack, then press.
7. On lower edge of garment: lay front facing, right sides together, along garment hem line and sew. Trim corner and turn onto wrong side. Press hem allowance onto wrong side, serge or finish edge and sew hem.
8. Apply fusing to sleeve hem. Sew elbow seam and sleeve seam. Press seam apart and turn sleeves right side out. Press sleeve hem allowances onto wrong side.
9. Make a gathering stitch along sleeve cap for ease. Sew to armhole, matching notches and easing along sleeve cap.
10. Sew in shoulder pads.
11. Sew lining together. Sew the lining to sleeve hems, front facing outer edges, and back neck facing. Pin the lining near vent carefully. Trim the lining round the vent excluding enough for turning under, and slip-stitching to vent. Serge the lower edge of lining, turn onto wrong side and topstitch.
12. Make buttonholes on right front and sew buttons on left.

**TECHNICAL DRAWING:**

