

Sewing Pattern — Coat 5021

Recommendations on fabric: velour of 150 cm width

You will also need: lining, fusing, 8 buttons, shoulder pads for raglan sleeve.

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Back part – 1 folded piece
2. Front part – 2 pieces
3. Back sleeve – 2 pieces
4. Front sleeve – 2 pieces
5. Front band – 2 pieces
6. Lay-down collar – 2 folded pieces
7. Back neckline facing – 1 folded piece

Lining:

8. Back part – 1 folded piece (excluding the width of neckline facing)
9. Front part – 2 pieces (excluding widths of front bands)
10. Back sleeve – 2 pieces
11. Front sleeve – 2 pieces

Fusing: Apply the fusing to wrong side of front bands, collar, back neckline facing, flaps. Press the fusing additionally to hem allowance.

INSTRUCTIONS:

1. Stitch relieve seams of back part and back sleeves. Topstitch seams at back part's right side.

2. Stitch one of front parts to front sleeve. Topstitch seams at front part's right side.
3. Stitch shoulder seams and sleeves' upper seams.
4. Stitch inner collar into back/front necklines. Stitch shoulder seams of front bands and back neckline facing. Stitch outer collar into front bands' neckline/facing.
5. Lay front bands on front parts right sides together, and pin them to edgings; pin edges of outer collar and inner one together. Process the coat neatly along edgings and collar. Press allowances of seams joining inner collar and back neckline facing apart and stitch them together.
6. Stitch side seams and lower seams of sleeves. Sew garment's hem. Sew front bands to garment hem.
7. Sew sleeve hems under.
8. Sew shoulder pads.
9. Stitch lining details together. Stitch the lining to inner edges of front bands and back neckline facing. Sew the lining under.
10. Make buttonholes into right front part, sew buttons on left one.

TECHNICAL DRAWING:

