

Sewing Pattern — Coat 5020

Recommendations on fabric: fabric suitable for coats of 150 cm width

You will also need: lining; fusing; 4 buttons; shoulder pads

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 3 cm on garment hem; 4 cm on sleeve hem; 1 cm on all other seams

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches. They must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Fabric:

1. Collar – cut 2
2. Center front – cut 2
3. Center back – cut 2
4. Side back – cut 2
5. Side front – cut 2
6. Back neck facing – cut 1
7. Upper sleeve – cut 2
8. Lower sleeve – cut 2

Lining:

9. Pocket sacking – cut 2
10. Center front – cut 2 (excluding front self-facing)
11. Center back – cut 2 (excluding widths of back neck facing)
12. Side back – cut 2
13. Side front – cut 2
14. Upper sleeve – cut 2
15. Lower sleeve – cut 2

Fusible interfacing: apply the interfacing to wrong side of front self-facing, back neck facing, lower edges of off-set welts. Apply additional strip of interfacing to hem allowance.

INSTRUCTIONS:

1. Sew pocket sacking, right sides together, to pocket entrance on center front. Snip front allowance diagonally to front corners. Turn sacking onto wrong side. Topstitch pocket entrance edge up to corner at 1.8 cm distance. Sew side front above pocket entrance, snipping allowance of center front diagonally to upper corner. Press seam towards center front. Sew edges of sacking to lower side front (from inside). Baste sacking side edges under center front. Topstitch along side front seam to pocket entrance at 1.8 cm distance.
2. Sew center back seam down to vent mark, press seam apart. Press vent seam allowances toward left.
3. Sew side backs to center backs. Clip into curves and press seams open. Sew shoulder and side seams, press seams apart. Sew front self-facing to back neck facing, press seams apart.
4. Fold front self-facing onto right side, sew neckline up to the mark. Snip neckline allowance close to the mark, trim corners. Turn front self-facing onto wrong side. Pin collar right sides together, sew outer edge, clip into curves, trim corners, and turn right side out. Sew outer collar into neckline, right sides together. Sew inner collar to neckline facing. Press seam allowances apart. Press allowances of seams joining inner collar and back neck facing apart and topstitch along joining seam.
5. At the hem: turn front self-facing onto right side. Sew lower edge of facing. Turn facing onto wrong side. Press garment hem allowances onto wrong side and hem by hand.
6. Press vent left edge onto wrong side, sew to hem allowance. Press self-facing of right side of vent onto wrong side, sew to hem allowance. Pin the vent along matching lines. Topstitch left back at vent's top along marking catching vent's edges.
7. Sew sleeve seams, press seams apart. Make a gathering stitch along sleeve cap for ease. Sew sleeves into armholes, matching marks and adjusting ease.
8. Sew shoulder pads.
9. Sew lining together same as main fabric. Sew the lining to sleeve hems, and inner edges of facing. Pin the lining at vent segment carefully. Cut the lining at vent segment; do not forget about seam allowances! Fold lining hem under, and sew to vent edges. Fold and topstitch hem of lining a few cm shorter than garment.
10. Make buttonholes in right front, sew buttons on left one.

TECHNICAL DRAWING:

