

## Sewing Pattern — Coat 5006

Recommendations on fabric: fabric suitable for coats

You will also need: lining, fusible interfacing, 4 buttons, shoulder pads

If the pattern has a double line around it, the seam allowances are included.

**Note:** By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guide lines are printed on pattern

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches. They must match up with corresponding pieces.



### **CUTTING:**

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

### **Main fabric:**

1. Lower back – cut 2
2. Side back\_2 – cut 2
3. Side back\_1 – cut 2
4. Center back – cut 1 on fold
5. Back neck facing – cut 1 on fold
6. Half-belt – cut 2
7. Off-set welt – cut 4
8. Pocket sacking – cut 2
9. Center front –cut 2
10. Front band facing – cut 2
11. Side front\_2 – cut 2
12. Side front\_1 – cut 2
13. Upper sleeve – cut 2
14. Lower sleeve – cut 2

### **Lining:**

15. Upper sleeve – cut 2
16. Lower sleeve – cut 2
17. Back – cut 1 on fold
18. Front – cut 2

**Fusible interfacing:** Apply the interfacing to wrong side of front band facings, back neck facing, lower parts of off-set welts and half-belt. Additionally, apply interfacing to hem allowance.

**INSTRUCTIONS:**

1. Sew lower back center seam, press seam apart. Match notches, tack a pleat. Then sew the pleat along upper allowance, a bit above marked line.
2. Sew center back to lower back, sew side back 1 and 2 to center back. Press seams apart.
3. Sew half-belt right sides together, leaving an opening for turning. Turn belt right side out and press. Slipstitch opening closed. Make a decorative stitch along belt edges at 0.5 cm distance. Fix the half-belt to back with buttons.
4. Sew off-set welt along outer edges, turn right side out, and press. Pin the welt on right side of side front part\_2, matching welt's upper edge to the notch, match welt's open edges to edge of side front part\_2; pin sacking's upper part on the welt, tack all details together. Lay sacking's lower part on right side of side front part\_1. Sew off-set welt and sackings. Sew side fronts 1 and 2 to center fronts. Turn sackings onto wrong side, adjust them and sew outer edges. Topstitch off-set welt short edges on front with a decorative stitch.
5. Sew shoulder and side seams. Press seams apart.
6. Sew center seam of outer self collar with front band facing. Sew shoulder seams of front band facing and back neck facing. Sew inner collar into garment neckline, sew outer collar into facing neckline. Press joining seam allowances apart.
7. Pin facing right sides together to center front; pin edges of outer/inner collars. Sew center front and collar. Press allowance of seam joining inner collar and back neck facing apart and topstitch allowance from inside. Sew lower edge of facing along hemline.
8. Sew garment hem.
9. Sew sleeve seams, process vents in elbow seams. Make a gathering stitch along sleeve cap for ease. Sew sleeves into armholes matching notches and adjusting ease.
10. Sew in shoulder pads.
11. Sew lining together same as main fabric. Sew lining to inner edges of facing and to sleeve hems. Turn lower edge of lining onto wrong side and topstitch. Turn right side out. Press.
12. Make buttonholes on right front, sew buttons on left one.

**TECHNICAL DRAWING:**

