

Sewing Pattern — Blouse 4293

Recommendations on fabric: natural or mixed thin blouse fabric

You will also need: fusing; 6 buttons.

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

SEAM ALLOWANCE: hem of the garment – 1.2 cm, along contour of the flounce-coquille - 0 cm; all other seams – 1cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Back part - 2 details
2. Front part - 2 details
3. Placket - 4 details
4. Stand-up collar – 2 details
5. Flounce — 2 details
6. Back part of sleeve – 2 details
7. Front part of sleeve – 2 details

Fusing:

1. Stand-up collar – 1 detail
2. Placket – 2 details

INSTRUCTIONS:

1. Apply fusing to plackets and outer stand-up collar.
2. Fold stand-up collar details right sides touching and overstitch. Start and finish the stitch exactly near marked line of connecting seam. Slash seam allowances on rounded parts. Turn ready stand-up collar out and press.
3. Sew waist, shoulder and bust darts on back part and on front part. Press depths of shoulder and waist darts towards center of corresponding details, depths of bust darts - upwards. Sew center edge of back part, press seam onto left side and serge.

4. Cut flounce in spiral. Serge outer edge of the flounce with thin rolled seam. Put flounce onto front part between notches and fix along the edge.
5. Fold plackets right sides touching and overstitch along outer edge. Turn details right side out and press. Stitch outer placket to front part, press seam allowances towards the placket. Turn inner placket inside and topstitch into connecting seam.
6. Sew side and shoulder edges, press seam onto back part and serge.
7. Sew outer stand-up collar into the neckline, turn inside open edge of lower stand-up collar and topstitch into outer stand-up collar connecting seam.
8. Serge hem of sleeve, press onto wrong side and topstitch. Put back part of sleeve onto front part of sleeve, leveling notches, and fix along top edge. Sew sleeve into armhole, slash seam allowances near notches, press and serge.
9. Cut bias tape of 4 cm wide and as long as lower part of the armhole + 6 cm. Fold bias tape in half lengthwise wrong sides together and press. Fold the bias tape with the edge of the armhole from the right side, leaving tails, and overstitch. Fold bias tape to wrong side, slash seams and topstitch along the fold onto main detail. Press the seam.
10. Serge hem of the garment, press onto wrong side and topstitch.
11. Serge buttonholes on right placket, sew buttons on left placket.

TECHNICAL DRAWING:

