

Sewing Pattern — Jacket 4167

Recommended fabric: suiting or coat fabrics of natural or mixed fibers.

You will also need: lining, fusible interfacing, 11 buttons, shoulder pads, sleeve heads.

If the pattern has a double line around it, the seam allowances are included.

Seam allowance: on hem and sleeve hem - 4.0 cm, other seams - 1.8 cm.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

(On the pattern pieces, “beam” means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.)

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Main fabric:

1. Center back – cut 2
2. Side back – cut 2
3. Side front – cut 2
4. Center front - cut 2
5. Front band facing –cut 2
6. Collar– cut 2
7. Upper sleeve – cut 2
8. Lower sleeve – cut 2
9. Back neck facing – cut 1

Lining:

1. Side back – cut 2
2. Side front – cut 2
3. Upper sleeve – cut 2
4. Lower sleeve – cut 2
5. Center back – cut 2
6. Center front – cut 2
7. Pocket bag – cut 4

Fusible interfacing:

Front band facing, back neck facing, inner collar

INSTRUCTIONS:

1. Apply fusible interfacing on front band facing, back neck facing, inner collar, armhole edge on front part and back. Apply interfacing on pockets marks on center and side fronts.
2. Sew and press darts on back toward center. Sew darts on front, trim dart depth. Press dart to the center and topstitch.
3. Sew back sides to center backs. Clip into curves of seam allowance and press toward center. Sew back center seam, press seam open.
4. Lay pocket bags on right side of side and center fronts. Sew bag to the pocket gate allowance. Turn the side front seam and topstitch on bag.
5. Sew relief cuts of front part and bag. Cut allowance at the beginning and end of pocket gate, press allowances open, pressing the pocket.
6. Sew shoulder seams, press open. Sew side seams, press open.
7. Sew back neck facing to front band facing, press seam open.
8. Sew outer collar into jacket's neckline. Sew front band facing to back neck facing, press open seams. Sew inner collar to front band facing and back neck facing. Clip curves and press. Sew facing to jacket, right sides together, and sew outer collar and inner collar with one seam. Trim corners, clip into curves, press. Turn jacket out, press. Press the hem.
9. Sew elbow side of sleeve, press seam open. Sew sleeve together, press seam open. Press sleeve hem.
10. Sew a gathering stitch along sleeve cap for ease. Sew sleeve into armhole, matching notches and adjusting ease. Sew in shoulder pads and sleeve heads.
11. Sew lining together, press seams open. Sew sleeve seams together, leaving an opening in the right front seam for turning. Sew sleeve linings to armholes of lining.
12. Sew lining to inner side of front band facing and back neck facing. Slipstitch allowances of inner collar close to seams.
13. Sew lining to jacket and sleeve edges. Turn jacket out through the opening in sleeve. Slipstitch the opening closed.
14. Topstitch the front stand, outer collar, jacket edge, and sleeve edge.
15. Make buttonholes on right front and right front of collar. Sew buttons on left front.

TECHNICAL DRAWING:

