

Sewing Pattern — Shirt 6056

Recommendations on fabric: elastic fabric of 150 cm width.

You will also need: fusing; 1 zipper

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Main fabric:

1. Patch pocket – 1 piece
2. Back part – 1 folded piece
3. Front part – 2 pieces
4. Collar – 2 folded pieces
5. Back sleeve – 2 pieces
6. Front sleeve – 2 pieces

Fusing: collar.

INSTRUCTIONS:

1. Apply the fusing to wrong side of collar.
2. Sew front middle seam below closure mark.
3. Fold pocket upper part allowance to right side and stitch to side edges. Turn upper allowance and pocket other edges allowance to wrong side. Topstitch the pocket along upper edge and topstitch on front left part along line of coinciding.
4. Sew side seams, stop stitching at 8 cm above slit mark. Sew sleeve lower seams.
5. Fold garment hem and sleeve hems to right side and stitch along slit edges strictly to slit mark. Fold hem upper edge downwards at slit mark level, and pin. Stitch the rest of side seams and sleeve upper seams. Turn allowances to wrong side and topstitch.
6. Sew sleeves into open armholes and topstitch along joining seam close to seam.
7. Sew the zipper under front slit edges with its teeth hidden.
8. Sew collar details along outer contour. Turn the collar right side out and press. Sew inner collar into neckline; fold outer collar under and stitch along joining seam to wrong side. Topstitch the collar.

TECHNICAL DRAWING:

