

## Sewing Pattern — Hooded blouse 4161

Recommendations on fabric: natural or mixed, medium stretch knit fabric

You will also need: decorative cord

If the pattern has a double line around it, the seam allowances are included.

**Note:** By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.



Seam allowance: top edges of lower front and of back – 2 cm; lower edges of top of front and of back – 2 cm; front stand edge - 0 cm; outer edge of hood – 3 cm; lower edges and edges of sleeve – 2 cm; all other edges – 0.7 cm

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

### **CUTTING:**

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

### **Advice:**

Knit fabric pieces are sewn together with special stretch-stitch or narrow zig-zag stitch. Seam allowance on hem is stitched with twin needles to save stretchiness. Pieces can also be sewn together with 3 or 4 – thread serger. When serging, cut seam allowances to 0.6 – 0.8 cm.

### **Fabric:**

1. Upper front - cut 2
2. Upper back – cut 2
3. Lower front– cut 1 on fold
4. Lower back – cut 2
5. Sleeve – cut 2
6. Hood - cut 2

### **INSTRUCTIONS:**

1. Sew center back seam on upper and lower backs, serge and press toward left.
2. Sew shoulder seams. Serge and press toward back.
3. Sew hood seam, serge and press toward left.
4. Sew hood into the neckline, serge seam.
5. Serge edge of upper center fronts and hood, turn onto wrong side and topstitch.
6. Sew sleeve into open armhole, matching notches.
7. Sew sleeve seam and side seam of upper part in one stitch.
8. Make buttonholes on lower front. Sew side seams of lower front and back. Sew upper and lower sections together at 2-3 cm. Serge and press seam downwards. Stitch at 0.5 cm off the seam allowance edge, to create the casing.
9. Serge lower edge of garment and sleeve edges. Turn seam allowances onto wrong side and topstitch.
10. Run the cord through the casing.

### **TECHNICAL DRAWING:**

