

## Sewing Pattern — Dress 4156

Recommendations on fabric: fabric suitable for dresses.

You will also need: invisible zipper, fusing.

If the pattern has double contour, seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance 1 cm on all edges. Hem – 2 cm, slit - 2 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.


### **CUTTING:**

Main fabric:

1. Central back part – 2 details
2. Side back part – 2 details
3. Side front part – 2 details
4. Central front part – 2 details
5. Stand-up collar – 4 details
6. Front neckline facing – 1 detail

Fusing:

1. Stand-up collar – 2 details
2. Front neckline facing – 1 detail



---

## **INSTRUCTIONS:**

1. Apply fusing to stand-up collar, front neckline facing.
2. Sew relieve seams on back part. Press seam allowances towards center and serge. Serge separately central edges of central back parts.
3. Sew relieve seams on front part. Press seam allowances towards edge and serge. Sew central front parts, serge and press to the left/
4. Serge outer edge of front neckline facing. Put facing onto front part right sides together and overstitch neckline. Slash seam allowances in corners and near relieve seams, turn facing to the wrong side and press.
5. Sew shoulder seams. Serge and press onto back part.
6. Sew central back seam from zipper marker to slit, press apart seam and slit.
7. Turn inner edge of inside stand-up collar to the wrong side and topstitch. Put together facing details right sides together and overstitch upper and side edges. Start and stop stitching exactly at the marked central line.
8. Sew outer stand-up collar into neckline. Press seam allowances onto stand-up collar. Sew in zipper. Topstitch central edge of inner stand-up collar onto zipper band. Turn facing the right side out and press. Topstitch the folded edge of inner stand-up collar onto seam.
9. Cut bias tape 4 cm wide and of the length equalling armhole length. Fold bias tape in half lengthwise wrong sides together and press. Put bias tape onto armhole from the right side and overstitch, turn bias tape onto wrong side and topstitch along fold onto main detail. Press the seam.
10. Sew side seams, press seam allowances onto back part and serge.
11. Serge the hem. Turn seam allowance onto wrong side, press and topstitch. Topstitch seam allowances of the slit.

**TECHNICAL DRAWING:**

