

## Sewing Pattern — Shirt 7205 (height 80-134 cm)

Recommendations on fabric: cotton, viscose, polyester.

You will also need: fusing; 8 buttons.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: on top edge of pocket – 3 cm, on side and upper edges of sleeve placket — 0.5 cm, all other seams – 1cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING:**

Fabric:

1. Back yoke - 1 detail
2. Back part - 1 detail
3. Right front part - 1 detail
4. Left front part - 1 detail
5. Left placket — 1 detail
6. Pocket — 1 detail
7. Sleeve placket – 2 details
8. Sleeve – 2 details
9. Collar – 2 details
10. Stand-up part of collar – 2 details
11. Cuff — 4 details

Fusing:

1. Collar – 1 detail
2. Stand-up part of collar – 1 detail
3. Cuff – 2 details

## **INSTRUCTIONS:**

1. Apply fusing to cuffs, top collar and inner stand-up part of collar.
2. Fold top collar with lower right sides together. Overstitch ends and outer edge of collar. Cut the seams. Turn collar out, straighten and press. Press inside lower edge of inner stand-up part of collar at 1 cm and topstitch at 0.7 cm. Fold stand-up part details right sides together, leveling upper edge, insert ready collar between them, level notches and sew, oversteitching ends of stand-up part at the same time. Turn ready collar out and press.
3. Press top edge of pocket first at 1 cm, and then again at 2 cm inside and topstitch. Press side and lower edges of pocket at 1 cm and topstitch according to markers onto left front part.
4. Put the placket with its right side onto wrong side of left front part and oversteitch the edge of the band. Fold the placket to right side, turn inside unworked edge and topstitch onto front part at 0.5 cm off the fold. Put decorative stitch at 0.5 cm off the band's edge.
5. Press one-piece placket of right front part along band line, turn inside open edge at 1 cm and topstitch along inner edge of the placket.
6. Make 1 bow pleat on back part and fix it on top edge. Stitch yoke to back part. Serge the seam and press it upwards. Stitch yoke to front part. Serge the seam and press it upwards. Put decorative stitch along yoke and back part / front part connecting seams at 0.1 cm off the seam.
7. Sew top stand-up part of collar together with the collar into the neckline, press the seam towards stand-up part. Topstitch lower stand-up part of collar into top stand-up part connecting seam.
8. Work the vent: Slit the sleeve on marked line, slashing the corner in top part of the slit. Turn section from the slit up to marked line that is 1.5 cm twice inside at 0.5 cm and topstitch. Fold the placket in half lengthwise right sides together and oversteitch the corner up to cross notch. Cut off seam allowances close to the stitch, slash seam allowance near the end of the stitch. Turn the placket out, press and stitch up along fold-line from below up to cross notch at 0.1 cm. Fold the placket with the sleeve right sides together and connect with inner side along the marked line. Slash sleeve near the end of the stitch crosswise from the slit up to connecting line. Fold the placket to right side, turn inside open edge and stitch. Align the placket with marked line on the sleeve and topstitch top corner along contour and along cross notch.
9. Sew the sleeve into open armhole. Serge the seam, press it to front part and topstitch at 0.1 cm.
10. Sew edges of sleeves, sewing side seam at the same time. Serge seams and press them to back part. Make and fasten pleats according to markers.
11. Turn inside lower edge of outer cuff detail at 1 cm and topstitch at 0.7 cm. Fold cuffs pairwise right sides together and oversteitch, leveling on top edge. Turn cuffs out and press. Stitch inner side of cuff to the sleeve. Topstitch outer side of cuff into connecting seam.
12. Serge hem of the garment, press onto wrong side and topstitch.
13. Serge buttonholes and sew buttons on cuffs and on collar. Serge buttonholes on right front part, sew buttons on left front part.

**TECHNICAL DRAWING:**

