

Sewing Pattern — Dress 7018

Recommendations on fabric: wool/mixed fabric

You will also need: fusing of 35 cm length and 90 cm width; 8 bead buttons of 14 mm diameter

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Front upper part – 2 pieces
2. Side upper front part – 2 pieces
3. Side upper back part – 2 pieces
4. Back upper part – 1 piece
5. Placket – 2 pieces
6. Sleeve – 2 pieces
7. Collar – 2 pieces
8. Cuff – 2 pieces
9. Side bow – 4 pieces
10. Frill – 2 folded pieces
11. Sleeve facing – 2 pieces
13. Back skirt – 1 folded piece

Fusing: collar; placket's half-width.

INSTRUCTIONS:

1. Apply the fusing to wrong side of outer collar and placket's half-width.
2. Stitch shoulder seams of front/back parts, neaten allowances, press them apart. Do the same for front/back side part.
3. Press frill along the center right side out, tack along open edge and gather open edge to adjust it to joint front/back relieve length.
4. Pin the frill with its bending to front upper part's middle on right side of joint front//back relieves.
5. Fold side bow along the center wrong side out and stitch long and one of short edges. Turn the detail right side out, press and make decorative stitch.
6. Pin side folded side bows on right side of side front/back relieves as marked.
7. Stitch front/back relieves coinciding marks and joining the frill and side bows. Press allowances to upper front part's middle ling and continue decorative stitching.
8. Stitch skirt side seams, press skirt hem into wrong side and stitch with double stitch.
9. Gather skirt upper edge slightly to adjust it to upper part's lower edge. Stitch waist seam, press it upward and make decorative stitch.
10. Make a slit into the sleeve. Lay the facing on the sleeve right sides together coinciding edges, then stitch at $\frac{1}{4}$ of facing width. Round sleeve edge with the facing, fold the rest of facing ($\frac{1}{4}$ of facing width) under and stitch along the bending coinciding it and previous seam. Press facing's upper edge into wrong side and tack along the edge.
11. Ease sleeve cap slightly with narrow stitches between marks and pull the cord till sleeve cap coincides to armhole. Moist the fabric and iron pleats. Pin sleeves to the garment coinciding marks. Stitch sleeves to garment at sleeve side.
12. Gather sleeve hems slightly to adjust them to cuff length. Fold the cuff along the center wrong side out, stitch short edges and turn right side out. Stitch reinforced cuff to sleeve hem; press cuff's open edge in and stitch to the sleeve along previous seam. Continue decorative stitch along cuff's perimeter.
13. Stitch collars right sides together along outer edges, turn the detail right side out and press.
14. Lay downfolded collar on upper front part's right side coinciding marks and shoulder seams. Stitch inner soft collar to neckline. Press allowances toward the collar, fold reinforced outer collar's open edge under and stitch to neckline.
15. Make decorative stitch along the collar.
16. Fold the placket along the center wrong side out and stitch short edges. Turn the detail right side out and press.

17. Lay the placket with its bending to side seam on front edging's wrong side and stitch soft placket to front edging. Press allowances toward the placket. Fold outer reinforced placket's edges under and stitch to front edging making decorative stitch along placket's perimeter.

18. Make buttonholes into right placket and into cuffs.

19. Sew buttons.

TECHNICAL DRAWING:

