

Sewing Pattern — Blouse 4307

Recommendations on fabric: natural or mixed silk.

You will also need: fusible interfacing, 4 buttons.

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

SEAM ALLOWANCE: on hem - 2 cm, all other seams - 1 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.



CUTTING:

(On the pattern pieces, “beam” means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.)

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Main fabric:

1. Back yoke – cut 2
2. Front yoke – cut 2
3. Lower back part — cut 1 on fold
4. Lower front part — cut 1 on fold
5. Sleeve — cut 2
6. Cuff — cut 2

Interfacing:

1. Cuff - cut 2

INSTRUCTIONS:

1. Apply interfacing to cuffs.
2. Sew shoulder seams on outer and inner yokes. Press apart the seam. Place yokes right sides together and sew neckline. Clip into curves of seam allowances, turn right side out and press. Treat yokes as one-layer in the next steps.
3. Sew a gathering stitch on the top edge of lower front part between notches and gather. Sew lower front to front yoke. Serge seam allowances and press them upwards.
4. Sew a gathering stitch on the top edge of lower back between notches and gather. Sew lower back to back yoke. Serge seam allowances and press them upwards.
5. Make a slit on sleeve according to marked line. Cut bias tape from main fabric 4 cm wide and as long as slit's double length + 4 cm. Fold the bias tape in half lengthwise and press. Press outer seam allowances towards center. Sew the bias tape to the slit of sleeve.
6. Sew a gathering stitch along cap of sleeve for ease. Sew the sleeve into armhole, matching marks and easing along cap. Serge seam allowance and press toward sleeve.
7. Sew side edge and sleeve edge together as one. Serge seam allowance and press it towards back.
8. Sew a gathering stitch on lower edge of sleeve and gather.
9. Fold the cuff in half, right sides together, and sew short sides and the long side. Start the stitch exactly near marked line of cuff and sleeve connecting seam. Trim seam allowances near the notch, turn cuff out and press. Stitch outer side of cuff to lower edge of sleeve. Turn inside inner side of cuff and topstitch into connecting seam.
10. Turn lower edge of the garment twice to wrong side, press and topstitch.
11. Make buttonholes on cuffs. Sew on buttons.

Wear the blouse with the belt.

TECHNICAL DRAWING:

