

Sewing Pattern — Skirt 4330

Recommended fabric: natural or mixed suiting fabric.

You will also need: interfacing, blind zipper.

If the pattern has a double line around it, the seam allowances are included.

Seam allowance: all seams - 1 cm, hem of the garment – 3 cm.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

(On the pattern pieces, “beam” means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.)

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Main fabric:

1. Center back – cut 2
2. Side back – cut 2
3. Center right front – cut 1
4. Center left front — cut 1
5. Side front — cut 2
6. Back facing – cut 2
7. Upper yoke – cut 2
8. Right yoke — cut 2
9. Left yoke - cut 2

Interfacing:

1. Back facing— cut 2
2. Upper yoke – cut 1
3. Left yoke — cut 1
4. Right yoke — cut 1

INSTRUCTIONS:

1. Apply interfacing to yokes and facings.
2. Sew backs to center backs. Clip into curves, serge and press toward center.
3. Serge seams of center backs separately. Then sew backs together from zipper mark down to hem. Press seam allowances apart including opening for zipper. Sew in zipper.
4. Sew left and right side fronts to center front. Clip into curves, serge and press toward center. Stop at mark for vents.
5. Apply interfacing to wrong side of edges for vent on front pieces. From right side, mark vent fold-line. Press center fronts on vent fold-line. On side fronts, press only vent seam allowance onto wrong side. Serge seams of front separately on each piece. Serge vent seam allowances. Align center front over front sides and topstitch top edge of the vent to vent's corner. Press seam allowances towards center, press vent seam allowances and slipstitch or machine stitch as desired.
6. Place yokes of center front, right sides together, and sew upper edge. Trim seam allowance and turn right side out. Sew upper edge of left yoke, inserting front yoke between them. Turn left yoke downwards and press. Sew upper edge of right yoke, inserting left and upper yokes between them. Turn right yoke downwards and press. Sew yoke to front. Serge seam and press up.
7. Serge lower edges of back facings. Sew back facings to backs.
8. Pin front and back skirt sections right sides together. Match side edges, and opened out edges of back facing with edges of opened out yoke. Sew side seams. Serge and press seam toward back. Tack facing at side seams and back facing to zipper tape by hand.
9. Serge hem of the skirt, press onto wrong side and hem by hand.

TECHNICAL DRAWING:

