

Sewing Pattern — Coat 4333

Recommendations on fabric: natural or mixed fabric suitable for coats

You will also need: fusible interfacing; shoulder pads; sleeve heads; 6 buttons; decorative piping with cord (approx. length is shown on lower front part pattern piece)

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowance: all seams - 1 cm, on hem of the garment and hem of sleeve - 3.5 cm, on lining edge- 2 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.



CUTTING:

Note: Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Advice:

Knit fabric pieces are sewn together with special elastic or narrow zig-zag stitch. Seam allowance on hem is stitched with twin needles to save stretchiness. Pieces can also be sewn together with 3 or 4 – thread serger. When serging, cut seam allowances to 0.6 – 0.8 cm.

Fabric:

1. Upper back – cut 2
2. Lower back – cut 1 on fold
3. Center upper front – cut 2
4. Side upper front – cut 2
5. Lower front — cut 2
6. Back neck facing – cut 1
7. Front facing (button stand) – cut 2
8. Upper sleeve – cut 2
9. Lower sleeve –cut 2
10. Sleeve strap — cut 4

11. Collar – cut 2
12. Collar stand – cut 2
13. Flap – cut 2

Lining:

1. Upper back – cut 2
2. Lower back – cut 1 on fold
3. Center upper front – cut 2
4. Side front – cut 2
5. Lower front — cut 2
6. Upper sleeve – cut 2
- Lower sleeve – cut 2
8. Flap – cut 2

ATTENTION: Front and back lining pieces are cut with main fabric pattern pieces except for the width of front facing (button stands) and back neck facing correspondingly.

Fusible interfacing: center front, outer collar, inner collar stand, front facings (button stands), back neckline facing, outer flap, sleeve strap, sections of the armhole and seam allowances on hem of the garment.

INSTRUCTIONS:

1. Apply fusible interfacing to details.
2. Sew flaps, right sides together, around 3 sides, inserting piping. Clip into curves, turn right side out and press.
3. Sew darts on upper back. Press darts towards center of back. Sew center back seam and press open. On lower back make and baste a counter pleat according to marks. Press seams toward center. Sew lower back to upper back. Press seam allowances upwards.
4. Sew side fronts to fronts. Press seam allowances towards center. Make a pleat on lower fronts according to marks. Press toward center. Sew lower front to upper front, inserting flap between details. Press the seam upwards.
5. Sew side and shoulder edges. Press the seam open.
6. Sew outer collar to outer collar stand, sew inner collar to inner collar stand. Press the seam open.
7. Sew the collar, right sides together, inserting piping. Start and end stitch exactly near marked line of collar stand connection. Turn collar right side out and press.
8. Sew shoulder edges of back neck facing and front facing (button stand) and press seams open.
9. Press hem. Place front facing (button stand) onto front, right sides together, pin and sew together, inserting piping. Stop sewing at the notch that shows the end of collar connection. Trim corners and turn facing to inside and straighten seams and press.
10. Sew outer collar into the neckline of main garment, and inner collar into the neckline of back and facing (button stand). Press the seam open. Tack allowances of collar connecting seams close to seams.
11. Make 2 sleeve straps. Sew, right sides together, on long sides, inserting piping. Place strap onto right side upper sleeve and baste on seams. Sew lower sleeve to upper sleeve, press seam open. Sew and press front sleeve seam open. Make a gathering stitch along the sleeve-cap for ease. Sew sleeve into armhole, easing around cap and matching notches. Sew in shoulder pads and sleeve heads.
12. Sew lining pieces the same way as the main fabric pieces, leaving an opening in left front seam of sleeve for turning. Sew lining to inner front facing (button stand) edges and back neck facing.

Sew lower corner of front facing (button stand). Sew bottom edge of lining to bottom edge of garment.

13. Sew lining to edge of sleeves. Turn coat right side out. Slipstitch the opening closed.

14. Make buttonholes on right front, sew buttons on left front.

15. Topstitch on back along outer and inner edge of pleat at 1 cm off the fold, catching hem.

TECHNICAL DRAWING:

