

Sewing Pattern — Dress 4375

Recommendations on fabric: fabric suitable for dresses in two colors.

You will also need: fusible interfacing, invisible zipper


If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowance: all seams - 1 cm; on hem of the dress – 2 cm

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Fabric 1:

1. Center upper front - cut 1
2. Center lower front - cut 1 on fold
3. Center back — cut 2
4. Upper sleeve – cut 2
5. Front neck facing — cut 1
6. Back neck facing —cut 2

Fabric 2:

1. Front inset — cut 1
2. Side front - cut 2
3. Side back — cut 2
4. Lower sleeve — cut 2

Fusible interfacing: front/back facings, vent

INSTRUCTIONS:

1. Apply the fusible interfacing to wrong side of front/back facings.
2. Sew center backs to side backs. Press seam allowances toward center. Apply fusing to wrong side of the vent on both back pieces. On right side, mark center seam line (vent fold-line). Serge center seam allowance together with vent's edge. Sew center edge of back from zipper mark down to vent's corner. Trim seam allowance on vent's corner. Press seam allowance of center seam and vent to left side. Press right side of the vent at 1 cm onto wrong side and topstitch. Topstitch seam allowances of the vent. Sew in the zipper.
3. Sew front inset to lower front. Serge seam allowance and press it upwards. Sew upper front to inset. Serge seam allowance and press it onto inset. Sew side front to center front. Serge and press seam toward center.
4. Sew shoulder seams and side seams, serge, and press seam toward back.
5. Make a gathering stitch on upper sleeve between notches and gather fullness. Sew upper and lower sleeves. Serge seam allowance. Serge lower edge of sleeve, turn onto wrong side and topstitch. Sew sleeve seam. Serge and press seam toward back. Make a gathering stitch along sleeve cap for ease. Sew sleeve into armhole matching marks and adjusting ease. Serge seam allowance.
6. Make two counter pleats on front neckline and baste on top edge.
7. Sew shoulder seams of the neckline facings. Press seam apart. Serge outer edge of facings. Pin the facing right sides together to neckline and sew. Clip into curves, understitch, and press facing to wrong side of garment. Tack the facing to shoulder seams and zipper tape.
8. Serge lower edge of garment, press onto wrong side, and topstitch.

TECHNICAL DRAWING:

