

Sewing Pattern — Coat 4383

Recommendations on fabric: fabric suitable for coats
(gabardine, cashmere, tweed)

You will also need: fusible interfacing; lining; shoulder pads; 6
buttons, sleeve heads

If the pattern has a double line around it, the seam
allowances are included.

Note: By default, seam allowances are NOT included (single
line) and will need to be added when laying out and cutting
details.

Seam allowance: all seams -1 cm; hem of the garment and
hem of sleeve - 3 cm

Attention! First of all, please print all the paper patterns and
lay them out at the width of fabric you plan to use (usually
from 90 to 150 cm) to see how much fabric you will need.
Don't forget to take into account pieces to be duplicated or cut
on a fold.

When sewing the garment, pay attention to notches. They
must match up with corresponding pieces.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the
fold, this is noted on the pattern piece. Mark all notches and other design features such as darts,
pleats etc. from the pattern onto your fabric.

Fabric:

1. Center back – cut 2
2. Upper side back – cut 2
3. Lower side back – cut 2
4. Upper side front – cut 2
5. Lower side front – cut 2
6. Center front – cut 2
7. Side front – cut 2
8. Placket – cut 2
9. Upper sleeve – cut 2
10. Lower sleeve – cut 2
11. Hood – cut 4
12. Front band facing – cut 2
13. Back neckline facing – cut 1
14. Belt – cut 1

Lining:

1. Center back – cut 2
2. Upper side back – cut 2
3. Lower side back – cut 2



4. Front – cut 2
5. Upper sleeve – cut 2
6. Lower sleeve – cut 2
7. Pocket sacking – cut 2

Fusible interfacing:

1. Center front – cut 2
 2. Front band facing – cut 2
 3. Back neckline facing – cut 1
- *Apply fusing to hem and hem of sleeve turnup

INSTRUCTIONS:

1. Apply interfacing to listed pieces.
2. Sew center back edge, press seam apart. Sew lower side and upper side backs, press seam apart. Sew center and side backs, press seams toward center.
3. Apply fusing to allowance of side front upper edge. Place pocket sacking onto right side of side front and stitch on pocket opening. Turn lining to wrong side and topstitch onto allowances. Lay detail on side front and fix on edges. Sew sacking edges, serge seam allowances.
4. Sew upper side and lower side fronts, press seam upwards. Stitch placket to center front, press allowances onto placket and topstitch at 0.7 cm from seam. Sew side and center backs, press seams to center.
5. Sew shoulder and side edges. Press seams apart.
6. Sew back neckline facing to front band facings, press seam apart.
7. Sew hoods together, pairwise, press seam allowances apart. Sew outer hood into neckline, and inner hood into neckline of front band facing and back facing. Clip into curves, press apart. Place together front band facings and main garment and make one stitch on front band edges and hood. Turn garment right side out, press. Fasten together allowances of hood connecting seam. Make it close to seams.
8. Sew front sleeve edge, press seam apart. Sew and press apart elbow sleeve seam.
9. Sew sleeves into armholes, matching notches. Sew in shoulder pads and sleeve heads.
10. Sew seams and darts on lining pieces, leaving an opening in front right sleeve seam. Place lining and main garment right sides together and sew to inner edges of front band facings and back neckline facing. Sew lower corner of front band, trim corners. Mark and press to wrong side hem of garment and hem of sleeves. Sew lining to hem of garment and hem of sleeves. Turn coat out through the opening in sleeve. Sew the opening closed.
11. Serge buttonholes on right placket, sew buttons. Serge first and third buttonholes on left placket, sew hidden buttons according to them.
12. Fold belt in half lengthwise right side together and stitch on contour, leaving an opening for turn-out. Trim allowances in corners, turn belt right side out. Sew opening closed.

TECHNICAL DRAWING:

