

Sewing Pattern — Dress 4120

Recommendations on fabric: fabric suitable for dresses, lace or guipure

You will also need: blind zipper; fusing; 6 buttons

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams - 1 cm; on lower edge – 1.5 cm, along vent – 6 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Facing of back part - 4 details
2. Middle central back part – 2 details
3. Middle side back part – 2 details
4. Back belt - 2 details
5. Lower central back part - 2 details
6. Lower side back part - 2 details
7. Lower side front part - 2 details
8. Lower central front part – 1 detail
9. Front belt - 1 detail
10. Middle side front part - 2 details
11. Middle central front part – 1 detail
12. Facing of front part - 2 details
13. Collar - 2 details
14. Cuff - 2 details

Lace:

1. Upper back part - 2 details
2. Upper front part - 1 detail
3. Sleeve - 2 details

Fusing:

1. Facing of back part - 2 details
2. Facing of front part - 1 detail
3. Collar - 1 detail
4. Cuff - 2 details

INSTRUCTIONS:

1. Apply fusing to details .
2. Sew relieve edges on middle parts of back part, press seam allowances towards center and serge. Sew relieve edges on lower parts of back part, press seam allowances towards center and serge.
3. Fold facings of back part right sides together, insert top part of back part between them and sew. Press seam allowances, turn facings downwards. Stitch middle back part to lower edge of outer facing, press seam onto the facing. Serge lower edge of inner facing and topstitch into connecting seam of top facing.
4. Stitch belt of back part to middle back part, press seam onto belt and serge. Stitch lower part of back part, to back part belt, press seam onto belt and serge.
5. Cut 5 cm on left lower central back part along vertical edge of the vent. Apply fusing to vent on both details of lower central back parts from wrong side. Mark middle seam line on right side (vent fold line). Press left part along vent fold line, press only seam allowance of right side of the vent (6 cm) on right part onto wrong side. Level details on middle seam and fix on top edge of the vent. Serge middle edge of back part separately on each detail . Serge seam allowances of the vent. Sew middle edge of back part from zipper marker up to vent corner. Slash corner of vent seam allowance on right part. Press seam allowances of middle seam apart, press seam allowances of the vent and fix them with machine stitch. Sew in zipper from top edge up to notches.
6. Sew relieve edges on middle parts of front part, press seam allowances towards center and serge. Sew relieve edges on lower parts of front part, press seam allowances towards center and serge.
7. Fold facings of front part right sides together, insert top part of front part between them and sew. Press seam allowances, turn facings downwards. Stitch middle part of front part to lower edge of outer facing, press seam onto the facing. Serge lower edge of inner facing and topstitch into top facing connecting seam.
8. Stitch belt of front part to middle part of front part, press seam onto belt and serge. Stitch lower part of front part to front part belt, press seam onto belt and serge.
9. Sew shoulder and side edges, press seam onto back part and serge.
10. Fold details of collar right sides together and overstitch ends and outer edge of collar. Start and finish the stitch exactly near marked line of collar connecting seam. Cut seam allowances in corners, slash on rounded parts. Turn collar out, straighten and press.
11. Sew lower collar into the neckline, slash seam allowances and press onto collar. Turn open edge of top collar and topstitch into connecting seam.
12. Serge longitudinal edges of sleeve. Stitch loosely along lower edge and gather ruffles. Sew edge of sleeve from rounded part up to marker, press seam allowances apart.
13. Fold cuff in half lengthwise right sides together and overstitch short sides. Start and finish the stitch exactly near marked line of cuff connecting seam. Press seam allowances, turn cuff the right side out. Stitch cuff with outer side to hem of sleeve, press seam onto cuff. Turn seam allowance of inner side of cuff and topstitch into connecting seam.
14. Serge lower edge of the garment, press onto wrong side and topstitch.
15. Serge buttonholes on cuffs and sew buttons.

TECHNICAL DRAWING:

