

Blouse With Buttons - Sewing Pattern #4471

Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: 10 buttons; fusible interfacing;

Seam allowances: all seams 1 cm; seam allowance for hem of blouse — 1.5 cm; seam allowance for hem of sleeve — 2 cm; seam allowance for fly piece of sleeve — 2 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back - cut 2
2. Front - cut 2
3. Front inset — cut 1
4. Front buttonstand facing — cut 2
5. Back sleeve - cut 2
6. Front sleeve - cut 2

7. Front neck facing — cut 2
8. Back neck facing — cut 1

Fusible interfacing:

1. Back neck facing — cut 2
2. Front neck facing — cut 2
3. Front buttonstand facing — cut 2

INSTRUCTIONS:

1. Apply fusible interfacing to facings.
2. Sew and serge center back seam. Seam Allowance press towards left.
3. Sew side and shoulder seams. Serge seams and press towards back.
4. Clip into seam allowance of lower edge of front near notch. Serge lower edge. Fold inside onto wrong side and topstitch.
5. Sew shoulder seams of facings, press seam apart. Serge facings along outer edge. Serge outer edge of buttonstand facing. Sew buttonstand facing to neckline facing. Press towards neckline facing. Pin together facings and blouse right sides together and sew corner, along outer edge of buttonstand and along neckline. Clip into curves, trim away corners and fold onto wrong side.
6. Serge all edges of front inset. Fold inside lower edge and topstitch. Place inset under buttonstand edges of front and pin together. (right front is on top). Topstitch seam allowances of facings onto blouse, at the same time sewing inset to fronts along curved lines.
7. Sew sleeve seam. Serge and press towards back. Serge slanting edges and hem of sleeve continuously. Fold inside lower edge and topstitch. Fold inside seam allowances of slanting edges and topstitch. Baste together parts of sleeves along the upper edge. Sew sleeves into armholes matching notches.
8. Sew on buttons according to notches.

TECHNICAL DRAWING:

