

Sewing Pattern — Dress 4287

Recommendations on fabric: fabric suitable for dresses

You will also need: blind zipper

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: hem of the dress – 3.0 cm; along the vent – 6 cm; all other seams -1 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Central back part - 2 details
2. Side back part - 2 details
3. Side front part - 2 details
4. Central front part - 1 detail
5. Collar - 2 details
6. Strap – 1 detail

INSTRUCTIONS:

1. Cut off 5 cm along vertical edge of the vent on left central back part. Apply fusing to wrong side of the vent on both details of central back part. Mark center seam line (vent fold line) from the right side. Press left part along vent fold line, on right part press only seam allowance of right side of the vent (6 cm) onto wrong side. Align details on center seam and fix along top edge of the vent. Serge center edge of back part separately on each detail. Serge seam allowances of the vent. Sew center edge of back part from neckline edge up to the vent's corner. Slash away corner of vent's seam allowance on right part. Press apart seam allowances of center seam, press seam allowances of the vent and fix them with machine stitch.
2. Sew princess seams on back part, press seam allowances towards center and serge.

3. Sew princess edges of front part. Slash seam allowance near top notch of left side front part. Press seam allowances to side edge, serge.
4. Sew shoulder seams, press seam onto back part, serge.
5. Cut bias tape of 4 cm wide and as long as the armhole + 3 cm. Fold bias tape in half lengthwise wrong sides together and press. Fold the bias tape with the edge of the armhole from the right side and overstitch. Fold bias tape onto wrong side, slash seams and topstitch along the fold onto main основную. Press the seam.
6. Fold details of collar right sides together and overstitch ends and outer edge between "O" notches. Cut seam allowances in corners, slash on rounded parts and near notches, turn collar right side out, press. Sew outer side of collar into the neckline, turn inner side inside and topstitch into connecting seam.
7. Fold the strap in half lengthwise right sides together and overstitch long side. Turn right side out, press, placing the seam in the center of the details. Serge short sides. Round ends of collar with the strap, shaping a bow. Fasten the strap to the dress, straighten ends of collar and sew to the dress with several stitches. Make and fasten some pleats on collar above back part center seam.
8. Serge separately left side edges. Sew left side edge, leaving a section for zipper open. Press apart the seam. Sew in zipper. Sew right side edge, press seam onto back part and serge.
9. Serge hem of garment. Fold onto wrong side, press and undersew with invisible stitches.

TECHNICAL DRAWING:

