

S3070 Skirt With Asymmetric Yoke And Pleated Fly Piece

Recommended fabrics: natural/mixed fabrics suitable for skirts

Ease: approximately 5/8 inch around waist and approximately 1.5 inch around hips.

You will also need: lining, fusible interfacing ,zipper, hook and eye.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included.

- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. You are welcome to use the Online Fabric Estimator to make calculations. Alternatively, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



PRINTING:

Please use Adobe Reader software to open your PDF pattern. You can get Adobe Reader free of charge at this link - <https://get.adobe.com/reader/>.

Make sure you print your patterns at actual size (100%% scale or None) and on single sides of plain A4 paper. Verify that the print out size is to the correct scale by measuring the test square on the first page. The upper edge of the square features a centimeter scale, and the bottom edge features an inch scale.

Trim top and/or right margin of the pages where you see the scissors symbols. In the center of each page, the number of row and column is printed, separated by / sign. Construct layout pages according to these marks (for example, page marked 2/3 is in the second row and in the third column). Align pages using margins and tape or glue together.

CUTTING:

Note on cutting:

Lay out your pieces according to straight of grain as marked on the pattern pieces.

Some pieces will be cut on the fold, the corresponding edge will then be marked with a fold mark. Kindly pay attention to notes regarding type of fabric and quantity of required pieces on a block. For example, [Main, Interfacing - cut 1+1] on a pattern piece means that you need to cut 1 piece as is and 1 mirrored piece from the main fabric as well as from interfacing.

Make sure to mark all notches and other design features such as pleats etc. from the pattern piece onto your fabric. When sewing the garment, pay attention to notches, they must match up.

Self

- (A) Front Pleated Piece - cut 1 + (optionally 1 in self or contrasting fabric)
- (B) Front Left Yoke - cut 1
- (C) Front Right Yoke - cut 1
- (D) Left Front - cut 1
- (E) Right Front - cut 1
- (F) Side Back - cut 1 +1
- (G) Center Back - cut 1 +1
- (H) Back Yoke - cut 1 +1
- (I) Back Facing - cut 1 +1
- (J) Front Facing - cut 1 on fold

Interfacing

- (B) Front Left Yoke - cut 1
- (C) Front Right Yoke - cut 1
- (H) Back Yoke - cut 1 +1
- (I) Back Facing - cut 1 +1
- (J) Front Facing - cut 1 on fold

Lining

- (K) Back Lining - cut 1 +1
- (L) Front Lining - cut 1

* The capital letters in brackets correspond to pattern blocks as seen in Online Fabric Estimator and in pattern blocks preview on the right.

INSTRUCTIONS:

1. Apply fusible interfacing to back and front waistband facings.
2. Sew Left Front to Left Front Yoke, matching notches. Grade seam, serge and press towards bottom.
3. Sew Right Front to Right Front Yoke, matching notches. Serge and press towards bottom.
4.
 - a) In case you make Front Fly piece double, pin fly pieces right sides together and sew along lower edge. Turn right side out and press. Baste fly pieces together along side seam, upper edge and center edge. Treat as one Fly Piece in the future.
 - b) In case your Fly Piece is single, turn seam allowance along lower edge under twice and topstitch. Remember that the wrong side of this edge is partly visible in folds.
5. Pin Fly Piece onto Left Front from the right side, right side together. Pin Right Front on top of the Fly Piece and Left Front, wrong side of fly piece to right side of right front. Remember to match notches. Sew seam from upper to lower edge, sewing the fly piece in place at the same time.
6. Make and baste pleats on the Fly Piece. First, fold fly piece towards right front along the marked pleat and press. Then fold the other two pleats in such a way that bulk of the pleat is directed towards right side seam. You will find marking on the upper edge of Left Front Yoke for the first fold, and marking on the upper edge of Right Yoke for the second fold. Baste together upper edge of fly piece with waistline and side seams of right front and fly piece. The lower edge of the Fly Piece along side seam should match the upper notch on Right Front. The resulting piece is referred to as Front in the future.
7. Sew Center Backs to Side Backs matching notches. Serge and press towards center.
8. Pin Back Yoke onto lower back from the right side, right sides together, matching notches. Clip into curves, serge and press towards Back Yoke.
9. Pin Backs to Front matching seams of yoke. Sew, serge and press towards back.
10. Serge center back edges separately. Serge seam allowances of the vents separately. Pin together Right Back and Left Back. Sew center back seam from notch for zipper down to vent corner. Press vent seam allowances to left side edge. Press right side of the vent at 1 cm and topstitch. Topstitch along vent marking. Press apart center back seam, including the slit for zipper. Sew in zipper.
12. Sew darts on Front Lining and on Back Linings.
13. Sew Front Facing to Front Lining, matching center front. Serge and press towards lining.
14. Sew Back Facing to Back Lining. Serge and press towards lining.
15. Serge side edges separately, sew side seams on lining and waist facings, and press apart.
16. Serge center back seam on linings and facings separately. Sew back center seam on lining from notch to vent

corner. Press apart, including the slit for zipper.

17. Serge the hem on lining, turn under and topstitch. Attach seam allowances along vent on lining to self vent.

18. Pin waist facing with lining onto skirt from the right side, right sides together, and sew along waist. Turn facing onto the wrong side and press. Slip stitch seam allowances of facings and linings to zipper tape. Sew a hook and eye near waist on the back.

19. Hem the skirt by hand or machine as desired.