Jacket With A Bow - Sewing Pattern #4082



RECOMMENDED FABRICS: Lightweight suiting fabrics made from natural or blended fibers, coordinating fabric: heavyweight silk.

YOU WILL ALSO NEED: Fusible interfacing; lining fabric; thin shoulder pads; 1 button.

SEAM ALLOWANCES: All seams – 1 cm. Sleeve hem allowance – 3.5 cm.

Note on seam allowances:
- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:
Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.

CUTTING:

Note on cutting:
On the pattern pieces, “beam” means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.
When sewing the garment, pay attention to notches, they must match up.

From main fabric:

1. Center Back – 2 pieces
2. Side Back – 2 pieces
3. Side Front – 2 pieces
4. Center Front – 2 pieces
5. Center Front Facing – 2 pieces
6. Back Neckline Facing – 1 piece
7. Upper Sleeve – 2 pieces

8. Lower Sleeve – 2 pieces
9. Upper Bow – 1 piece
10. Bow Loop – 1 piece
11. Back Hem Facing – 1 piece

From silk:

1. Lower Bow – 1 piece

From lining fabric:

1. Center Back – 2 pieces
2. Side Back – 2 pieces
3. Side Front – 2 pieces
4. Center Front – 2 pieces
5. Upper Sleeve – 2 pieces
6. Lower Sleeve – 2 pieces

ATTENTION: The back and front lining pieces are cut excluding the width of the back neckline facing, back hem facing and center front facings, respectively.

FUSIBLE INTERFACING: Center Front Facings, Back Neckline Facing, Back Hem Facing, Center Front, Side Front, Lower Bow, sleeve hems.

INSTRUCTIONS:

1. Apply fusible interfacing to the pieces. Apply additional fusible stay tape along the front neckline.

2. Stitch the dart on the center front piece. Press the dart upwards. Stitch the princess seam on the front piece and press the seam allowances open.

3. Stitch the dart on the center back piece. Stitch the princess seams on the back pieces and press the seam allowances open. Stitch the center back seam and press open. Stitch the shoulder and side seams of the jacket and press open.

4. Stitch the shoulder seams of the back neckline facing and center front facings and press open. Stitch the back hem facing to the center front facings. Press the seams open.

5. Fold the bow loop in half lengthwise, right sides together, and stitch along the long edge. Turn the loop right side out and press, positioning the seam in the center of the piece.

6. Place the upper and lower bow pieces right sides together and stitch along the upper and lower edges. Turn the pieces right side out, shape the edges and press. Place the bows one on top of the other and secure them

together along the raw edge.

7. Place the bow loop on the front piece according to the markings, with the loop seam facing upwards and the free end directed towards the armhole. Topstitch the loop to the front piece along the marked line. Stitch the bows to the right front neckline. Wrap the loop around the bow and stitch its free end to the neckline edge.

8. Stitch the elbow seam of the sleeve, easing in the upper sleeve section and matching the notches. Press the seam allowances open. Press the sleeve hem allowance to the wrong side. Unfold the hem allowance, stitch the front sleeve seam and press the seam allowances open.

9. Set the sleeves into the armholes, matching the notches and easing in the upper part of the sleeve caps. Attach the shoulder pads.

10. Stitch the seams of the lining pieces and set in the sleeves, leaving an opening in the left elbow seam for turning the jacket right side out later. Stitch the lining to the inner edges of the center front facings and the other facings.

11\. Place the center front facings and attached facings on the front pieces, right sides together, and pin. Stitch along the front edges, front neckline, back neckline and jacket hem, working from the front piece side. Understitch the front edge seam allowance onto the center front facing, stitching 0.2 cm from the seam.

12. Stitch the lining to the sleeve hems. Turn the jacket right side out. Sew the turning opening closed.

13. Work a buttonhole on the right front piece and sew a button onto the left front piece.

TECHNICAL DRAWING:

