

## Dress With Decorative Yoke - Sewing Pattern #4724

Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: dress zipper, fusible interfacing, 4 buttons.


Seam allowances: all seams 1 cm; seam allowance for hem of dress – 3.0 cm, seam allowance along vent – 6 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



## CUTTING:

### Note on cutting:

*On the pattern pieces, “beam” means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.*

*When sewing the garment, pay attention to notches, they must match up.*

Main fabric:

1. Center back - cut 2
2. Side back - cut 2
3. Center front – cut 1 on fold
4. Back yoke - cut 2
5. Front yoke - cut 2
6. Front inset - cut 1

7. Back neck facing - cut 2
8. Front neck facing - cut 2
9. Front inset facing - cut 1
10. Sleeve - cut 2
11. Cuff - cut 2

Fusible interfacing:

1. Back neck facing - cut 2
2. Front neck facing - cut 2
3. Front inset facing - cut 1
4. Cuff - cut 2

## INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew side backs to center back, press seam allowances towards center and serge.
3. Sew back yoke to lower back, press seam allowances towards yoke and serge.
4. Trim away 5 cm on left center back along vertical edge of the vent. Apply interfacing to the vent on both sides of center back on the wrong side. Mark center seam line (vent fold-line) from the right side. Press left part along vent fold, on the right side press onto wrong side only the seam allowance of right side of vent (6 cm). Align pieces along center seam and baste together along upper edge of vent. Serge seam allowances of vent. Sew center back seam from notch to vent corner. Clip into seam allowance of vent in corner on right part. Press apart center seam, press seam allowances of the vent and sew them together by machine. Sew in zipper.
5. Sew darts on front, press bulk towards center.
6. Sew shoulder seams, press seams towards back and serge.
7. Sew shoulder seam on front neckline facing and back neckline facing, serge outer edge. Pin facing to dress right sides together, adjusting neckline edges, and sew. Clip into curves, turn facing under and press. Slip stitch facing to shoulder seam and zipper tape
8. Pin front inset facing to inset right sides together and sew outer edge. Trim away corners, turn facing under and press. Serge according to markings buttonloops. Pin inset onto yokes and baste together along lower edge.
9. Sew front yoke to lower front, serge and press towards bottom.
10. Sew side seams, press seams towards back and serge.

11. Sew sleeve seam, serge and press. Sew sleeves into armholes, matching notches. Serge and press.
12. Sew cuff into a ring, press seam apart. Fold cuff in half lengthwise and press right side out. Sew outer side of cuff to sleeve, press seam allowances towards sleeve. Fold edge of inner cuff under and stitch-in-the-ditch into seam of outer cuff.
13. Serge bottom edge of dress, press onto wrong side and topstitch or hem as desired.
14. Sew on buttons on yokes according to holes.

**TECHNICAL DRAWING:**

