

Blouse With Decorative Collar - Sewing Pattern #4733

Recommendations on fabric: natural/mixed silk fabrics.

You will also need: fusible interfacing; 4 buttons.

Seam allowances: seam allowance along hem of garment — 2 cm;
other seams - 1 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, “beam” means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back – cut 1 on fold
2. Front — cut 2
3. Stand collar – cut 1
4. Sleeve — cut 2
5. Cuff — cut 2

Fusible interfacing:

1. Cuff — cut 2

INSTRUCTIONS:

1. Sew shoulder darts, press bulk towards center.
2. Cut slit on back along the marked line. Cut bias tape from main fabric (or take ready), its width should equal 4 cm and length should equal two lengths of slit +4 cm. Fold bias tape in half lengthwise and press. Press outer seam allowances towards center. Finish the slit with bias tape.
3. Serge center front edges separately. Sew center front seam, press seam apart, pressing the slit at the same time. Sew a decorative stitch along slit at 0.1 cm. Make and baste pleats on front neckline (fold bulks from center).
4. Sew side and shoulder seams, press seams towards back and serge.
5. Cut (or take ready) bias tape, its width should equal 3 cm and its length should equal 10 cm. Fold tape in half lengthwise and stitch at 0.3 from fold. Trim seam allowances and turn the piece right side out. Cut the rolled piece in two halves and adjust the length of loop buttonhole.
6. Fold stand collar right sides together and sew short edges and the area between round markings. Clip into seam allowances near notches, turn right side out stand collar onto right side, press.
7. Sew left outer edge of stand collar into neckline, press seam allowances at stand collar. Twist the stand collar and sew right outer side into neckline, press seam allowances at stand collar. Turn edge of inner stand collar under and stitch in the ditch.
8. Cut slit on sleeve along the marked line. Cut bias tape from main fabric (or take ready), its width should equal 4 cm and length should equal two lengths of slit +4 cm. Fold bias tape in half lengthwise and press. Press outer seam allowances towards center. Sew bias tape to slit of sleeve (pin bias tape to slit edge from the right side and sew, fold bias tape onto wrong side and topstitch onto garment along fold line).
9. Sew sleeve seam, serge and press. Sew a gathering stitch along hem of sleeve and gather fullness.
10. Sew sleeves into armholes, serge and press.
11. Fold cuff in half lengthwise, right sides together and sew short sides and corner. Start stitching exactly at the line which marks the seam between cuff and sleeve. Clip into seam allowances near the notch, turn cuff right side out and press. Sew outer side of cuff to lower edge of sleeve. Fold inside inner side of cuff and stitch in the ditch.
12. Serge hem of garment, press onto wrong side and topstitch.

13. Fold stand collar in half, insert loop buttonholes between the sides on the right part and topstitch. Sew on buttons onto left side. Sew on buttons onto cuffs.

TECHNICAL DRAWING:

