

## PATTERN OVERVIEW

### Made-to-measure pattern:

The pattern is drafted by our proprietary software specifically for your measurements that you supply when making an online order. We strongly recommend that you request a free preview to check the style lines and the amount of fabric needed before ordering the paid version.

### Pattern features:

Sleeveless blouse with front fly pieces; button closure.

**Recommendations on fabric:** natural or mixed lightweight woven fabric.

**You will also need:** fusible interfacing, 7 buttons, bias tape (optional).

### Seam allowances:

If the pattern has double contour the seam allowances are included and are as follows: 1/2 inch on all edges, lower edge of blouse and center back seam – 1.5 inch.

Attention! Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

### Fabric requirements:

To estimate fabric requirements, get a free preview for the pattern in your size at [www.Lekala.net](http://www.Lekala.net) and use [Online Fabric Estimator](#). Alternatively you may print all the paper patterns and lay them out at the width of fabric you plan to use (usually 44 inches to 60 inches) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must match up.




## CUTTING:

Lay pattern pieces out using the straight of grain line. Some pieces may be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

### Main fabric:

1. Front - cut 2 (D)
2. Back - cut 2 (G)
3. Front placket - cut 2 (A)
4. Front collar (fly piece) - cut 4 (F)
5. Front yoke cut 2 (E) - cut 2
6. Back armhole facing - cut 2 (H)
7. Front armhole facing - cut 2 (I)
8. Stand collar outer piece - cut 2 (B)
9. Stand collar inner piece - cut 2 (C)



### Fusible interfacing:

1. Stand collar - cut 2 (B)
2. Front placket - cut 2 (A)

**INSTRUCTIONS:**

1. Sew darts on backs and fronts. Press shoulder darts towards center, bust darts - upwards, waist darts - towards center.
2. Sew center back seam. Serge and press seam towards left side seam.
3. Place front fly pieces pairwise right sides together and sew on side and lower edges. Grade seams, turn piece out, straighten and press.
4. Place front yoke to front right sides together, insert fly piece between them and sew. Serge and press seam towards yoke. Topstitch along the seam if desired.
5. Sew shoulder and side seams. Serge and press seams towards back.
6. Apply fusible interfacing to collar pieces and plackets.
7. Fold placket in half lengthwise wrong sides together, press. Sew top part of placket to front right sides together. Unfold. Turn under the edge of lower part of placket and sew into the seam from inside. Topstitch along placket perimeter at 0.5 cm from edges if desired.
8. Sew collars on center back seam. Press seam open. Place outer and inner collars right sides together and sew outer and side edges. Grade seams, turn collar right side out, straighten and press.
9. Sew outer collar into neckline. Press seam towards collar. Turn edge of lower collar under and topstitch into collar connecting seam.
10. Finish armholes with facings or bias tape.
11. Serge lower edge of blouse, turn under, press, and topstitch.
12. Make buttonholes on right front placket as marked. Sew buttons on left front placket.

---

*If you have any further questions regarding the pattern,  
please don't hesitate to contact us at [info@sewist.com](mailto:info@sewist.com).  
We are always happy to help!*

---

TECHNICAL DRAWING:

