

Sewing Pattern — Dress 4060

Recommended fabric: silk fabric suitable for dress.

You will also need: 1 invisible zipper, fusible interfacing.

If the pattern has a double line around it, the seam allowances are included.

Seam allowance: 1 cm on all edges. Seam allowance on the garment hem — 3 cm, sleeve hem — 1cm, vent — 6 cm.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.

CUTTING:

(The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.)

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Main fabric:

1. Left front — cut 1
2. Right front — cut 1
3. Center back— cut 2
4. Side back — cut 2
5. Sleeve — cut 2
6. Left collar — cut 2
7. Right collar — cut 2
8. Back facing —cut 2
9. Left front facing — cut 1
10. Right front facing — cut 2

Fusible interfacing:

1. Back facing — cut 2
2. Left front facing — cut 1
3. Right front facing — cut 1



INSTRUCTIONS:

1. Apply interfacing to facings.
2. On left center back cut 5 cm along vertical edge of vent. Apply interfacing to vent on both sides. Mark the line of center seam (vent fold) from the right side. Fold along vent fold line on back and press, fold seam allowance (6 cm) on right and press onto the wrong side. Pin together and baste on the upper edge of vent. Serge center back seam and vent separately. Sew central back seam from zipper marker to vent. Press the seam apart, including opening for zipper. Press vent seam allowances and baste with stitch. Sew in zipper.
3. Sew side back to center back, serge and press seams toward center.
4. On left front, make pleats as follows: start from lower pleat and work on the right side. Put together two lower markers and turn the depth downwards. Pin the pleat. Repeat for next two lower markers, and repeat for all pleats.
5. Sew front sides to center front. Trim seam allowance near upper marker on right front. Serge and press seam toward right.
6. Pin right collar, right sides together, and sew two outer edges. Trim corners and curves and turn right side out, and press. Repeat for left collar. Sew right collar to front side neck edge, sew left collar to neck and seam edge.
7. Sew shoulder seams, inserting left collar inside shoulder seam, serge and press toward back. Sew side seams, serge and press toward back.
8. Serge lower edge of sleeve, press onto wrong side and topstitch. Sew sleeves into armholes and press. Trim seam allowance of armhole and cap to 0.7 cm.
9. Cut bias tape 3.5 cm wide and of the length equal to that of armhole. Finish armhole seam with the bias tape. Press seam.
10. Sew center seams of front facings and shoulder seams of facings, serge outer edge, pin facing and dress together and sew back neckline, part of the right front side neckline and front neckline. Clip into curves, and turn facings onto wrong side. Fold seam allowance of back facing under, and hand-stitch to zipper tape. Topstitch along neckline close to seam, under collars. Topstitch collar edges.
11. Serge bottom edge of garment. Fold onto wrong side, press, and hand-stitch with invisible stitches.

TECHNICAL DRAWING:

