

Knit Tunic - Sewing Pattern #2095

Recommendations on fabric: well draping natural/mixed knit fabrics of high to medium stretchiness.

You will also need: knit bias tape, knit fusible interfacing.

Seam allowances: seam allowance for hem of garment - 2.0 cm, other seams - 1.0 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.

Note on working with stretchy fabric:

Knitted fabric pieces are sewn together with special elastic or narrow zig-zag stitch. Seam allowance on hems can be stitched with twin needles to save stretchiness. Pieces can also be sewn together with a serger. When serging, cut seam allowances to 0.6 – 0.8 cm.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Front – cut 1 on fold
2. Back – cut 2

- 3. Front yoke – cut 1
- 4. Collar – cut 2

Fusible interfacing:

- 1. Collar – cut 1

INSTRUCTIONS:

- 1. Apply fusible interfacing to upper collar.
- 2. Sew center back seam. Serge and press towards left.
- 3. Sew a gathering stitch along upper edge of front and gather fullness. Sew yoke to the upper edge of front. Serge and press towards top.
- 4. Sew shoulder and side seams, press seams towards back and serge.
- 5. Pin collars right sides together and sew around collars and collar fall. Clip into curves, trim away corners. Turn collar right side out and press. Sew outer edge of collar into neckline, press towards collar. Fold inside seam allowance of inner collar at 1 cm and stitch in the ditch.
- 6. Cut (or take ready) bias tape , its width should equal 4 cm and length should equal the length of armhole + 6 cm. Fold bias tape in half lengthwise right side out and press. Pin bias tape to armhole edge from the right side and sew. Fold bias tape onto wrong side, clip into seam allowances and topstitch onto main piece along the seam. Press seam.
- 7. Serge lower edge of garment, press onto wrong side and topstitch.

TECHNICAL DRAWING:

