

Sewing Pattern — Pants 4024

Recommendations on fabric: light-weight dress fabrics, chiffon

You will also need: fusible interfacing.

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowance: all seams -1 cm, on hem of main detail - 2.5 cm .

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Fabric:

1. Pants panel – cut 2
2. Back waistband/tie– cut 1
3. Front waistband/tie – cut 1
4. Lining – cut 2

Interfacing: Waistband/Tie

INSTRUCTIONS:

1. Apply interfacing to waistband section of waistband/tie.
2. Mark and sew darts on pants. Press darts towards center. Sew middle edge, serge and press.

3. Mark and sew darts on lining. Press darts towards center. Sew middle edge, serge and press. Serge seam allowance on hem of lining, press onto wrong side and topstitch.
4. Pin lining with main fabric, wrong sides together, match notches and seams and baste top and side edges. Now sew as one-layer. Serge side edges, turn inside and topstitch.
5. Serge bottom edge of pants, press onto wrong side and topstitch hem.
6. Fold back waistband/tie in half lengthwise, right sides together, and sew one short and long sides up to marker. Turn waistband/tie right side out and press ends. Stitch outer edge of the waistband/tie to top edge of the pants. Turn inner edge of the waistband onto wrong side and topstitch in top edge connecting seam. Sew the front waistband/tie the same way.

TECHNICAL DRAWING:

