

## Blouse With Scalloped Neckline - Sewing Pattern #2201

Recommendations on fabric: natural/mixed fabrics suitable for blouses, lace with scallops.

You will also need: fusible interfacing, 5 buttons.

Seam allowances: seam allowance for hem of garment — 2.0 cm, other seams - 1 cm, seam allowance on lower edge of sleeve - 0 cm. When cutting the sleeve, place the pattern block so that the scalloped edge of the fabric is along the sleeve hem.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



## CUTTING:

### Note on cutting:

*On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.*

*When sewing the garment, pay attention to notches, they must match up.*

Main fabric:

1. Back - cut 1 on fold
2. Front — cut 2
3. Center front facing — cut 2
4. Back neck facing - cut 1

Lace:

1. Sleeve — cut 2

Fusible interfacing:

1. Center front facing — cut 2
2. Back neck facing - cut 1

## **INSTRUCTIONS:**

1. Apply fusible interfacing.
2. Sew darts on front. Press bulk towards top.
3. Sew side and shoulder seams, press seams towards back and serge.
4. Sew and press apart shoulder seams of back neckline facing and buttonstand. Serge outer edge.
5. Place center front facing onto front right sides together, pin together and sew lower corner, along the center front edge and neckline. Trim seam allowances, clip into corners and along neckline. Turn buttonstands (center front edges) right side out, straighten seams.
6. Sew sleeve seam, press seams towards back and serge. Sew sleeves into armholes, matching notches. Serge and press.
7. Serge lower edge of garment, press onto wrong side and topstitch.
8. Make buttonholes on right front, sew on buttons on left front.

## **TECHNICAL DRAWING:**

