

Sewing Pattern — Top 4018

Recommendations on fabric: light-weight blouse fabric of natural or mixed fibers.

You will also need: fusible interfacing, 3 buttons

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowance: for all seams - 1 cm.

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Fabric:

1. Back – cut 1
2. Front- cut 1
3. Band (belt) - cut 1
4. Stand-up collar - cut 2

Interfacing:

1. Band (belt) – cut 1
2. Stand-up collar - cut 1

INSTRUCTIONS:

1. Apply interfacing to stand-up collar and band.
2. Cut a strip of bias tape to bind back slit opening. The length of the bias tape is equal to opening + 4 cm, the width – 5cm. Press the bias tape lengthwise right side out. Mark cut-line on the back, and cut. Open up back along cut line in straight line, Place bias tape on right side, aligning cut and sew. The seam's width along cut length is 0.5 – 0.7 cm, it declines to 0.2 cm in lower part of the cut. Fold bias tape onto wrong side, enveloping the seam, and topstitch in connecting seam.
3. Make a gathering stitch along upper edge of the front and gather fullness.
4. Sew right side seam. Serge and press seam toward back. Serge left side edges separately. Sew left side seam, from armhole to mark. Press seam open.
5. Cut a strip of bias tape from main fabric of 4 cm wide and length equal to armhole's length. Press the bias tape lengthwise right side out, pin to armhole edge and sew. Fold tape to the wrong side and topstitch along the folding.
6. Pin stand-up collar, right sides together, and sew outer and side edges. Clip into curves. Turn stand-up collar out and press. Press inner collar seam allowance under. Sew outer stand-up collar to neckline between marks for front and back. Sew inner stand-up collar into connecting seam. Topstitch. Press.
7. Fold band lengthwise, right sides together, and sew short sides. Trim corners and turn right side out. Make a gathering stitch on lower edge of garment and gather fullness. Sew outer edge of the band to lower edge of the garment. Press seam allowances onto band. Press inner edge of band onto wrong side and topstitch in upper band connecting seam.
8. Make buttonholes and sew buttons on stand-up collar and band.

TECHNICAL DRAWING:

