

Blouse With Inset - Sewing Pattern #2215

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: 1 button.

Seam allowances: seam allowance for hem of garment and hem of sleeve - 1.5 cm, other seams 1 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back yoke — cut 2
2. Side back - cut 2
3. Front yoke - cut 1
4. Side front — cut 2
5. Sleeve - cut 2

Main fabric 1:

1. Center back – cut 1 on fold
2. Center front — cut 1 on fold

INSTRUCTIONS:

1. Serge center edges of back yokes separately, press onto wrong side. Sew a fixing stitch along the edge of the slit at 0.1 cm.
2. Sew side backs to center back. Serge seams and press towards center. Sew back yokes to back, press seam allowances towards yoke and serge.
3. Sew side front to center front, press towards center and serge. Sew front yoke to front. Serge and press onto yoke.
4. Sew side and shoulder seams, press seams towards back and serge.
5. Cut (or take ready) bias tape, its width should equal 2.5 cm and its length should equal 5 cm for loop buttonhole. Fold tape in half lengthwise right sides together and stitch at 0.3 cm from fold. Cut away seam allowances close to seam, turn tape right side out and straighten rolled hem. Adjust length of the loop.
6. Cut (or take ready) bias tape, its width should equal 4 cm and length should equal the length of neckline + 4 cm. Fold bias tape in half lengthwise right side out and press. Pin bias tape to neckline from the right side, leaving loose ends, and sew. Fold bias tape onto wrong side, clip into seam allowances and topstitch onto main piece along the seam. Press seam. Sew button loop to the left back yoke.
7. Sew sleeve seam, serge and press towards back. Sew sleeves into armholes, serge and press.
8. Serge hem of garment and hem of sleeve, press onto wrong side and topstitch.
9. Sew button to right back yoke.

TECHNICAL DRAWING:

