

## Sewing Pattern — Blouse 4013

Recommendations on fabric: light blouse fabric of natural or mixed fibers.

You will also need: fusing, 8 buttons

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: on hem – 2 cm, other seams - 1 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING:**

#### Fabric:

1. Front part yoke – 2 details
2. Lower front part - 1 detail
3. Back yoke - 1 detail
4. Lower back part - 1 folded detail
5. Panel – 4 details
6. Upper sleeve part – 2 details
7. Lower sleeve part – 2 details
8. Cuff – 2 details
9. Facing neckline – 2 details
10. Pate – 4 details

#### Fusing:

1. Facing neckline – 1 detail
2. Cuff – 2 details
3. Panel – 2 details

---

## **INSTRUCTIONS:**

1. Apply fusing to panels, the facing neckline and cuffs.
2. Stitch loosely on upper edges of lower parts of front part and back part and gather ruffles.
3. Stitch lower parts of front and back parts to yokes. Serge seams and press upwards.
4. Fold panels pairwise right sides together and overstitch: left panel on outer edge till hem (till the angle beginning), right – on outer edge and angle till notches. Slash seam allowance on right panel on notch. Turn and press details. Slash seam allowance under panel on front part leaving 1mm to seam line. Stitch outer parts of panels to front part. Turn left panel onto right side, bending hem seam allowance inwards. Turn right panel onto right side, spreading lower angle from right side. Turn inside seam allowances of inner panels. Put decorative stitch on panels, sewing inner edge. Fix lower angle of right panel from right side.
5. Sew side and shoulder edges. Serge seams and press to back part.
6. Fold facings neckline right sides together and overstitch on inner edge and short sides. Start and finish stitching exactly near marked line of sewing facings to neckline. Turn onto right side, slashing on rounded parts. Sew in outer facing into the neckline. Turn inside seam allowance of inner facings and topstitch into outer facings connecting seam.
7. Cut lower part of sleeve according to markers. Cut bias tape of 4 cm length and of length equal to slit double length on sleeve. Fold bias tape in half lengthwise and press. Unfold the bias tape. Direct outer edges of bias tape into the center of bias tape and press. Fold again in half and press. Overstitch cuts on sleeve with bias tape.
8. Fold pates pairwise and overstitch on two long sides and angle. Turn onto right side, slashing seam allowances in corners, straighten and press. Stitch loosely and gather ruffles on top edge of lower part of sleeve. Sew lower and top parts of sleeve, putting pate into seam from wrong side. Sew sleeve seam. Serge and press on back part of sleeve. Sew sleeves into armholes. Serge and press.
9. Fold cuffs in half right sides together and overstitch short sides. Turn and press cuffs. Stitch outer side of cuff to sleeve. Turn inner side of cuff and topstitch in connecting seam.
10. Turn hem of the garment twice inside on 1 cm. onto wrong side and topstitch.
11. Serge buttonholes on right panel, cuffs and pates. Sew buttons on left part of front part, cuff and on sleeve.

**TECHNICAL DRAWING:**

