

Sewing Pattern — Jacket 4304

Recommended fabrics: natural or mixed, well-draping costume fabric

You will also need: interfacing; 1 button; shoulder pads; sleeve heads.

Seam allowances are included if your pattern has a double contour.

Seam allowances are NOT included if your pattern has a single contour, and need to be added when laying out and cutting pieces.



All seam allowances are 1 cm (3/4 ins.), except for the sleeve hem, where it is 3.0 cm (1.2 ins.)

Please note!

Before you begin, print all the paper pattern pieces and lay them out on the width of fabric you plan to use (usually from 90 to 150 cm, (35 to 59ins.)) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, be careful to match seam marks.

CUTTING:

Main fabric:

1. Center back – 2 pieces
2. Side back – 2 pieces
3. Side front – 2 pieces
4. Center front – 2 pieces
5. Lower back – 1 piece
6. Lower front – 2 pieces
7. Buttonstand – 2 pieces
8. Back neckline facing – 1 piece
9. Upper sleeve – 2 pieces
10. Lower sleeve – 2 pieces

Lining:

1. Center front – 2 pieces
2. Side front - 2 pieces
3. Center back – 2 pieces
4. Side back – 2 pieces
5. Lower back – 1 piece
6. Lower front – 2 pieces
7. Upper sleeve – 2 pieces
8. Lower sleeve – 2 pieces

PLEASE NOTE: Center front and center back lining pieces are cut using the main fabric pattern less the width of the buttonstand and back neckline facing respectively.

Interfacing: center front, collar, back neckline facing, along sleeve hem

INSTRUCTIONS:

1. Apply interfacing to pieces.
2. Sew darts on center back and press towards center. Sew and press apart princess seams on front and on back. Sew and press apart center seam of back part.
3. Sew and press apart side edges of the jacket. Sew shoulder seams, trim corners, press seam allowances apart. Sew buttonstand pieces together on the seam at the back of collar, press seam allowances apart. Sew collar into the neckline, press seam allowances apart.
4. Sew and press apart side edges of lower back and lower front pieces. Sew lining pieces as above. Fit lining inside main piece, right sides together, and sew lower edge. Trim seam allowances on rounded seams, turn right side out, press. Stitch lower part of the jacket to upper part (seam allowances of collars overhang by 1 cm).
5. Stitch together shoulder edges of back neckline facing and buttonstand facing. Trim corners and press seams apart. Sew edge of collar, press seam allowances apart. Sew collar into the neckline facing, press seam allowances apart.
6. Place buttonstand facing on center front pieces, pin together and stitch along the collar. Trim seam allowances on rounded seams. Turn collar out, straighten seams, press.
7. Sew and press apart elbow sleeve seam. Press sleeve hems. Sew and press apart front sleeve seam.
8. Sew sleeves into armholes according to notches, easing in on rounded part. Sew in shoulder pads and sleeve heads.
9. Sew the sleeve linings, leaving an opening in the front right seam of sleeve lining . Set sleeve linings into jacket sleeves.
10. Stitch lining to inner edges of collar and to back neckline facing. Turn collars with lining wrong side out and sew to the jacket, placing lower part between main fabric and lining. Stitch lining to sleeve hem. Turn jacket out through the slit in sleeve. Trim seam allowances along the collar. Sew the slit in sleeve closed.
11. Make a buttonhole on right front of jacket, sew the button on the left front of jacket.

TECHNICAL DRAWING:

