

Blouse With Wrap - Sewing Pattern #2447

Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing; 5 buttons.

Seam allowances: all seam allowances – 1.0 cm. Seam allowance for hem of garment – 1.5 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.



Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

- 1. Back cut 1 on fold
- 2. Front cut 2
- 3. Center front facing cut 2
- 4. Cuff cut 2
- 5. Collar cut 2
- 6. Stand collar cut 2
- 7. Back neck facing cut 2



8. Belt - cut 2

Fusible interfacing:

- 1. Collar cut 1
- 2. Stand collar cut 1
- 3. Cuff cut 2
- 4. Center front facing cut 2
- 5. Back neck facing cut 1

INSTRUCTIONS:

- 1. Apply fusible interfacing.
- 2. Fold belt in half lengthwise right sides together and sew longer edge and one shorter edge. Trim away corners, turn right side out and press.
- 3. Sew princess seam of right front, inserting belt according to notches. Serge. Sew princess seam of left front. Serge.
- 4. Serge side edges separately, serging the sleeve edges at the same time. Sew side edges, sewing the sleeve edges at the same time, from bottom to the mark for slit. Press seam apart.
- 5. Sew shoulder edges, sewing the sleeve edges at the same time. Press seams towards back and serge.
- 6. Pin together collars right sides together and sew ends and collar fall. Trim seam allowances, turn the collar right side out, straighten and press. Sew a decorative stitch around all edges. Pin together parts of stand collar, right sides together and sew, inserting collar. Start and stop stitching exactly at the marked seam of stand collar into neckline. Trim seam allowances, turn stand collar right side out and press.
- 7. Pin belt, right side down, onto right side of the right front and sew together along the center edge of front.
- 8. Sew shoulder edges of center front facing and of the back neckline facings. Press seam apart. Serge outer edge. Pin Center Front facing onto front and onto back and sew center front facings and neckline, inserting stand collar. Clip seam allowances, fold center front facing and facing onto wrong side. Slipstitch pieces together along the shoulder seams.
- 9. Sew a gathering stitch along lower edge of sleeve and gather fullness.
- 10. Fold cuff in half lengthwise, right sides together and sew shorter edges cuffs. Trim seam allowances, turn right side out and press. Sew outer side of cuff to sleeve, fold inside the seam allowance of inner cuff and stitch-in-the ditch into seam of outer cuff.



- 11. Serge the lower edge of garment, press onto wrong side and topstitch.
- 12. Make buttonholes and sew on buttons on fronts and on cuffs. Make the inner button hole. Sew on inner button.

TECHNICAL DRAWING:

