

Long Jacket - Sewing Pattern #2511

Recommendations on fabric: thin coat or natural/mixed suiting fabrics.

You will also need: lining; fusible interfacing; 1 button.

Seam allowances: all seams 1 cm. Seam allowance for hem of garment and hem of sleeve - 3.0 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back - cut 2
2. Front - cut 2
3. Upper sleeve - cut 2
4. Lower sleeve - cut 2
5. Center front facing - cut 2
6. Back neck facing - cut 1
7. Off-set welt - cut 2

Lining:

1. Back - cut 2
2. Front - cut 2
3. Upper sleeve - cut 2
4. Lower sleeve - cut 2
5. Small pocket bag - cut 2
6. Large pocket bag - cut 2

Fusible interfacing:

1. Center front facing - cut 2
2. Back neck facing - cut 1
3. Off-set welt - cut 2

Attention! Lining is cut using the pattern blocks for main fabric, except for the width of the center front facing and the back neckline facing.

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew center back seam, press seam apart.
3. Mark the position of pocket. Press welt in half lengthwise wrong sides together. Topstitch small pocket bag onto inner side of welt. Sew welt to front along lower marked line of pocket. Sew large pocket bag to front along upper marked line of pocket. Stop stitching near short marking lines of the pocket. Slash through pocket opening. Snip diagonally toward end of stitching at 1-1.5 cm from end of pocket opening. Turn welt and large pocket bag onto wrong side through the resulting opening. Sew a double back stitch lines near corners to fix ends of pockets. Sew together edges of pocket bags.
4. Sew shoulder and side seams, press seam apart.
5. Sew center edge of one-piece collar. Sew one-piece collar into neckline, clipping into seam allowance near corner.
6. Sew shoulder edges of center front facings and back neckline facing, press seam apart. Sew center collar seam. Sew collar into neckline facings, clipping into seam allowance near corner. Pin center front facing onto main piece, right sides together, pin together and sew center front edge, lapels, collar and lower edge. When stitching make sure to place the front piece on top. Topstitch seam allowance on buttonstand onto buttonstand. Place stitch line at 0,2 cm from seam. Turn center front facing onto wrong side, straighten, press.
7. Sew elbow seam on sleeve, press seam apart. Press hem of sleeve onto wrong side. Sew front seam on sleeve, press seam allowances towards lower part. Sew sleeves into armholes matching notches, press seam.

8. Fold under seam allowance along hem and press. Sew seams on lining, leaving an opening in left elbow seam of sleeve. Sew lining to back facing and to center front facing. Sew lining to lower edge of garment. Turn the garment right side out through the opening. Sew the opening closed.

9. On right front make button loop, on left front sew on button.

TECHNICAL DRAWING:

