

Tunic With Slanted Closure - Sewing Pattern #2600

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing; 5 buttons.

Seam allowances: Seam allowance for hem of garment and hem of sleeve - 1.5 cm; other seams - 1 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back - cut 1 on fold
2. Front right - cut 1
3. Front left - cut 1
4. Placket right — cut 1
5. Placket left — cut 1
6. Sleeve - cut 2

7. Collar - cut 2
8. Stand collar - cut 2

Fusible interfacing:

1. Placket right — cut 1
2. Placket left — cut 1
3. Stand collar - cut 1
4. Collar - cut 1

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Serge the inner edge of the left placket. Pin the left placket to the left front right sides together and sew the neckline. Clip seam allowances, turn placket onto wrong side, press. Topstitch onto the main piece along the marked line.
3. Pin the right placket to the right front right sides together and sew the neckline. Clip seam allowances, turn placket onto wrong side, press. Sew the left front to the right placket, serge, catching the loose end of the placket. Straighten the pieces, topstitch the right placket onto front, fixing the left front.
4. Sew shoulder seams, press towards the back and serge.
5. Pin upper collar to lower collar, right sides together. Sew ends of collar and collar fall. Trim seam allowances. Turn the collar right side out, straighten and press. Pin stand collars together, right sides together, insert the ready collar between them, adjust edges and sew, sewing the ends of stand collar at the same time. Start and stop sewing exactly at the marked line of seam between stand collar and garment. Turn finished collar right side out and press. Sew upper stand collar with collar into neckline, fold raw edge of lower stand collar and stitch-in-the-ditch along seam of upper stand collar.
6. Sew sleeves into armholes, serge and press. Sew side seams, sewing the sleeve edges at the same time, press towards the back and serge.
7. Serge hem of garment and hem of sleeve, press onto wrong side and topstitch.
8. Make buttonholes on right placket, sew on buttons onto left front.

TECHNICAL DRAWING:

