

Dress With Asymmetrical Collar - Sewing Pattern #2620

Recommendations on fabric: natural/mixed knit fabric of small stretchiness in contrasting or similar color.

You will also need: knit fusible interfacing; dress zipper.

Seam allowances: all seams 1 cm; seam allowance for hem of garment - 2 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.

Note on working with stretchy fabric:

Knitted fabric pieces are sewn together with special elastic or narrow zig-zag stitch. Seam allowance on hems can be stitched with twin needles to save stretchiness. Pieces can also be sewn together with a serger. When serging, cut seam allowances to 0.6 - 0.8 cm.

CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Upper center back - cut 2
2. Upper side back - cut 2



3. Lower back - cut 2
4. Upper center front - cut 1 on fold
5. Upper side front - cut 2
6. Lower front - cut 1 on fold
7. Sleeve - cut 2
8. Back neck facing - cut 1
9. Front neck facing - cut 1

Main fabric 1:

1. Collar — cut 2
2. Cuff - cut 2

Fusible interfacing:

1. Collar — cut 1
2. Cuff - cut 2
3. Back neck facing - cut 1
4. Front neck facing - cut 1

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew princess seams on upper back, press towards center, serge. Sew upper back to lower back, press towards top and serge.
3. Serge center back edges separately on each piece. Sew the center back seam from neckline to the first mark and from the second mark down to hem, press the seam apart. Sew in zipper.
4. Sew princess seams on upper front, press towards center, serge. Sew upper front to lower front, press towards top and serge.
5. Sew side and shoulder seams, press towards the back and serge.
6. Pin collars together, right sides together, and sew collar ends and collar fall. Clip into curves, trim away corners, turn collar right side out, press. Sew collar into neckline.
7. Sew the shoulder seams of the neckline facings, press the seam apart. Serge the outer edge. Pin facing to garment right sides together and sew the neckline (the collar is placed between the facing and the garment). Clip into curves, facings turn right side out onto wrong side and press. Slipstitch it to shoulder seams.
8. Sew sleeve seam, press towards back and serge. Sew sleeves into armholes, serge and press.
9. Sew cuff into a ring, press the seam apart. Fold cuff in half lengthwise right side out. Sew cuff to lower edge

of sleeve, press seam allowances towards sleeve and serge.

10. Serge bottom edge of dress, press onto wrong side and topstitch.

TECHNICAL DRAWING:

